



Configuration Guide for SAP Asset Information Workbench by Utopia for S/4HANA

Release 1909

Document History

The following table provides an overview of the most important document changes and approvals.

Version	Date	Description	Name
1.0	05-11-2019	Initial Version	Kuldeep Singh, Jyoti Das
2.0	20-03-2020	Updated for SP01	Kuldeep Singh.

Approval History

Version	Date	Description	Name
1.0	05-11-2019	Final version	Lyle Snyder
2.0	24-03-2020	Approved update for AIW 1909 SP01	Lyle Snyder

Table of Contents

1.	Introduction	6
1.1.	Purpose	6
1.2.	Target Audience.....	6
1.3.	Organization.....	6
2.	Prerequisites/Before You Start.....	6
2.1.	Prerequisite SAP OSS Notes.....	6
3.	Set Up Workflow.....	7
3.1.	Set Workflow Task to General	7
3.2.	Set Up Search.....	7
3.3.	Adjust Profile Parameters.....	7
3.4.	User Role.....	7
3.5.	Web Dynpro Applications	8
3.5.1.	Web Dynpro Application for POWL.....	8
3.5.2.	Web Dynpro Component for POWL.....	8
3.5.3.	Review POWL Configuration.....	9
3.5.4.	Maintain POWL Query Definition.....	9
3.5.5.	Maintain POWL Categories.....	10
3.5.6.	Maintain POWL Query Role assignment	10
3.5.7.	Maintain POWL Type definition	11
3.5.8.	Maintain POWL Type Role assignment	12
3.6.	Activate Services in SICF	12
3.7.	Number Ranges	14
3.8.	GenIL (Generic Interaction Layer) Component Adjustments.....	14
3.8.1.	GenIL (Generic Interaction Layer) Component Adjustments	14
3.9.	Prerequisite Notes.....	16
3.9.1.	Specific Prerequisite Notes	16
3.10.	Prerequisite BC-Set activation	16
3.10.1.	BC-Set for AIW	16
3.10.2.	BC-Set for HANA Search	18
3.10.3.	BC-Set for AIW NON-LAM system	18
3.10.4.	BC-Set for Cross Entity HANA Search Views	18
3.10.5.	BC-Set for Cross Entity Search Configuration Entries.....	20

3.11. External API to handle MDG-AIW	20
3.12. Prerequisites and configuration for AIN Integration	21
3.12.1. AIN Header Data Mapping	21
3.12.2. AIN Characteristics Value Mapping	21
3.12.3. AIN FLP URL Parameter maintenance	21
3.13. Configuration for GEF Integration	21
4. Configuration Process	21
4.1. Activation check for Data Model U1	21
4.2. Navigate User Interface.....	21
4.2.1. Link Log. Actions with UI Application and Bus. Act.: Standard Definition.....	21
4.2.2. Link Logical Actions with Business Activity: Standard Definition.....	22
4.3. Verify UI Modeling (Optional).....	23
4.4. Set up of Data Replication	23
4.4.1. Customizing for Data Replication Framework (DRF- AIW Specific).....	23
4.5. Set Up Search.....	24
4.5.1. Create the Search View	24
4.6. Verify Data Quality, Search Settings, and Duplicate Check.....	24
4.6.1. Configuration of the duplicate check for HANA search.....	24
4.7. Verify Remaining Process Modeling Settings.....	24
4.7.1. Mixed Multi-Object Change Request (MOCR)	24
4.8. Configuration Change Request Settings	26
4.8.1. Configuration Variant Splitter.....	26
4.9. Configure Workflow Tasks.....	26
4.9.1. AIW Parallel/Serial Workflow Process flow (4 step BRF+).....	26
4.10. Set Up the Rule-Based Workflow.....	29
4.10.1. Configure Rule-Based Workflow.....	29
4.11. Choose where you want to run SAP MDG	38
4.11.1. SAP NetWeaver Portal.....	38
4.11.2. SAP NetWeaver Business Client.....	38
4.12. Configure Process Quality Metrics (Optional).....	38
4.12.1. Change Request Priorities.....	39
4.12.2. Change Request Reasons	39
4.12.3. Change Request Rejections	39
4.13. Workflow Templates for SAP Asset Information Workbench by Utopia.....	39

4.13.1. WS80000007 – Multi-Object Change Request WF	39
4.13.2. WS80000008 - Utopia Rule-Based Sub WF for MOCR.....	42
4.14. Email or Notifications Configuration	47
4.14.1. Disclaimer.....	47
4.14.2. Email Configuration.....	47
4.14.3. Technical Details.....	53
4.14.4. Dependencies.....	54
4.14.5. Sample Emails/Notifications	54
4.15. SP01 Configuration	55
4.15.1. Pre-Requisite notes.....	55
4.15.2. Common Configuration	55
4.15.3. Equipment Configuration.....	56
4.15.4. Functional Location Configuration	59
4.15.5. Email Configurations	62
4.16. System Compatibility	62
4.17. Final Steps.....	62

1. Introduction

This document provides the information required to set up SAP Asset Information Workbench (AIW 1909) by Utopia.

1.1. Purpose

This Configuration Guide provides the information required to set up Master Data Governance (MDG) for Asset Information Workbench by Utopia (AIW 1909).

1.2. Target Audience

This guide is designed to help the following end-users:

- Functional and Technical consultants who configure the MDGIMG settings.
- System administrators who deploy and configure SAP Business objects.
- Solution Architects and Application end-users who refers to the guide while using the MDG applications.

1.3. Organization

This guide primarily consists of the following sections.

- Introduction
- Prerequisites/Before You Start
- Set Up Workflow
- Configuration Process

2. Prerequisites/Before You Start

You have successfully installed and configured UGI EAM 1909.

The BADI - /UGI7/AIW_RETAIN_FIELD for AIW Copy Hierarchy Create with different maintenance plant can be implemented if required (Optional).

Please check if the inheritance parameters are maintained as per section 2.4.2 in EAM Configuration Guide (Optional).

2.1. Prerequisite SAP OSS Notes

The following note is applicable for 1809 FPS02 release.

Note number	Short text	Application Component
2665808	Short dump in USMD_MC_SEARCH_REPLACE in Multi-Processing CR	CA-MDG-AF

3. Set Up Workflow

3.1. Set Workflow Task to General

Use the following steps to set the Workflow Task to General:

1. Run t-code SWDD.
The Workflow Builder is displayed.
2. Enter Workflow as WS80000008.
3. Click on 000073-Dialog Processing Task (TS80000022) from the Navigation area.
4. Click on  Agent assignment for task icon corresponding to Agent Assignment in the Task properties.
The Standard Task: Maintain Agent Assignment screen is displayed.
5. Click on the “Attributes” button.
The Attributes details dialog box is displayed.
6. Select the parameter as “General Task” and click Transfer.

3.2. Set Up Search

Refer UGI EAM 1909 Configuration Guide.

3.3. Adjust Profile Parameters

Refer UGI EAM 1909 Configuration Guide.

3.4. User Role

To successfully conduct the steps in the configuration process, you must have the following user role assigned in the PFCG transaction:

/UGI7/AIW_REQ: Asset Master Data Governance for AIW: Requester.

The following roles have been created for AIW.

Role Name	Description
/UGI7/AIW_MENU	SAP Asset Information Workbench by Utopia: Menu
/UGI7/AIW_REQ	SAP Asset Information Workbench by Utopia: Requester
/UGI7/AIW_SPEC_EQUI	SAP Asset Information Workbench by Utopia: Specialist-Equipment
/UGI7/AIW_SPEC_FUNCLOC	SAP Asset Information Workbench by Utopia: Specialist-Functional Location
/UGI7/AIW_SPEC_MPLAN	SAP Asset Information Workbench by Utopia: Specialist-Maintenance Plan
/UGI7/AIW_SPEC_MSPOINT	SAP Asset Information Workbench by Utopia: Specialist- Measuring Point
/UGI7/AIW_SPEC_OBJLINK	SAP Asset Information Workbench by Utopia: Specialist- Object Link
/UGI7/AIW_SPEC_OBJNETWRK	SAP Asset Information Workbench by Utopia: Specialist - Object Network
/UGI7/AIW_SPEC_PMBOMHDR	SAP Asset Information Workbench by Utopia: Specialist-Material BOM

/UGI7/AIW_SPEC_EQBOMHDR	SAP Asset Information Workbench by Utopia: Specialist-EQ BOM
/UGI7/AIW_SPEC_FLBOMHDR	SAP Asset Information Workbench by Utopia: Specialist-FL BOM
/UGI7/AIW_SPEC_WBSBOMHDR	SAP Asset Information Workbench by Utopia: Specialist-WBS BOM
/UGI7/AIW_SPEC_TLEQHDR	SAP Asset Information Workbench by Utopia: Specialist- Equipment-Task list
/UGI7/AIW_SPEC_TLFLHDR	SAP Asset Information Workbench by Utopia: Specialist- Funloc-Tasklist
/UGI7/AIW_SPEC_TLGNHDR	SAP Asset Information Workbench by Utopia: Specialist- General Tasklist
/UGI7/AIW_SPEC_WORKCNTR	SAP Asset Information Workbench by Utopia: Specialist- Work Center
/UGI7/AIW_STEW	SAP Asset Information Workbench by Utopia: Steward
/UGI7/AIW_MODEL	SAP Asset Information Workbench by Utopia: Menu

3.5. Web Dynpro Applications

Refer UGI EAM 1909 Configuration Guide. It should be in place since EAM configuration should already be completed. Do check it only when you encounter any issue related to this section.

3.5.1. Web Dynpro Application for POWL

Application: /UGI7/MDG_EAMWB_POWL_INBX is created for serving the POWL Inbox.

Application	/UGI7/MDG_EAMWB_POWL_INBX	Saved
<input checked="" type="button"/> Properties <input type="button"/> Parameters		
Description	MDG EAM Workbench POWL Inbox	
Component	/UGI7/MDG_EAMWB_POWL_INBX	
Interface View	POWL_WINDOW	
Plug Name	DEFAULT	
<input type="button"/> Help Links		

Application	/UGI7/MDG_EAMWB_POWL_INBX	Saved	
<input checked="" type="button"/> Properties <input type="button"/> Parameters			
<input type="button"/> Parameters			
Parameters	Value	Type	Description
WDREFERREDRENDERING	STAND_ONLY	WDUI_HTML_RENDER_MODE	HTML Render Mode
WDUIGUIDELINE	FIORI	WDR_APP_PROP_UIGUIDELINE	UI Guideline

3.5.2. Web Dynpro Component for POWL

Web Dynpro Component: /UGI7/MDG_EAMWB_POWL_INBX (AIW POWL Inbox) is created for serving the POWL Inbox.


Web Dynpro Component	/UGI7/MDG_EAMWB_POWL_INBX	Active
Description	MDG EAM WorkBench POWL Inbox	
Assistance Class	/UGI7/_POWL_WD_PERSONALIZATION	

3.5.3. Review POWL Configuration

Personalization Application Hierarchy is created to describe the context in which one can use the Worklist.

t-code: FPB_MAINTAIN_HIER

Personalization Application ID: /UGI7/_POWL_EAMWB_APPLID



Change View "Personalization Hierarchy": Overview

Personalization Application	Description
/UGI7/_POWL_EAMWB_APPLID	POWL Application for AIW

Display View "Personalization Characteristics": Overview

Field Name	InputHelp	Grp Value	Interval	Single Val	Ref. Data Element
DEFAULT_QUERY	<input type="checkbox"/>	N None	M Multiple	M Multip...	POWL_QYERY_TY
LAYOUT	<input type="checkbox"/>	N None	M Multiple	M Multip...	POWL_LAYOUT_TY

3.5.4. Maintain POWL Query Definition


t-code: POWL_QUERY

Define the Standard Queries (content for Personal worklist)

Query ID: /UGI7/_POWL_EAMWB_QUERY_ID

Description: POWL Query for AIW

POWL type ID: /UGI7/_POWL_EAMWB_TYPE_ID



Edit Table Views: Initial Screen

Query ID	Description
/UGI7/_POWL_EAMWB_QUERY_ID	POWL Query for AIW

Edit Table Views: Initial Screen

New Entries Query Parameters Query Settings Layout variant Calculated Dates

Query ID: /UGI7/_POWL_EAMWB_QUERY_ID

View: Query definition

Description	POWL Query for AIW
POWL Type ID	/UGI7/_POWL_EAMWB_TYPE_ID
<input type="checkbox"/> Sync. call	
Layout	
Refresh Type	2 On Every Page Visit

3.5.5. Maintain POWL Categories

t-code: POWL_CAT

Define Categories. The categories are used on the portal interface as an organizational structuring element for the queries. Queries that are assigned to a category appear together in the same block.

Category: /UGI7/_POWL_EAMWB_CATEGORY

Description: POWL Query for AIW

Change View "Category definition": Overview

New Entries BC Set: Change Field Values

Category definition	
Category	Description
/UGI7/_POWL_EAMWB_CATEGORY	POWL Query for AIW

Change View "Category definition": Details

New Entries

Category	/UGI7/_POWL_EAMWB_CATEGORY
Category definition	POWL Query for AIW

3.5.6. Maintain POWL Query Role assignment

t-code: POWL_QUERYR

Define Query Visibility at Role level and assign a query to a role in this activity.

Application: /UGI7/_POWL_EAMWB_APPLID

Query Id: /UGI7/_POWL_EAMWB_QUERY_ID

Category: /UGI7/_POWL_EAMWB_CATEGORY

Change View "View: Query - Role assignment": Overview

New Entries Check

View: Query - Role assignment		
Application	Query ID	Category
/UGI7/_POWL_EAMWB_APPLID	/UGI7/_POWL_EAMWB_QUERY_ID	/UGI7/_POWL_EAMWB_CATEGORY

Change View "View: Query - Role assignment": Details

New Entries Check

Application	/UGI7/_POWL_EAMWB_APPLID
Role	
Query ID	/UGI7/_POWL_EAMWB_QUERY_ID

Category	/UGI7/_POWL_EAMWB_CATEGORY
Description	POWL Query for AIW
Category sequence no	1
Query sequence no	1
Tab sequence no	1
<input checked="" type="checkbox"/> Activate	

3.5.7. Maintain POWL Type definition

t-code: POWL_TYPE

POWL Type ID: /UGI7/_POWL_EAMWB_TYPE_ID

Description: Type ID for AIW

Feeder class: /UGI7/CL_MDG_EAM_WB_POWL_FEEDR

Change View "View: Type definition": Overview

New Entries Check

View: Type definition	
POWL Type ID	Description
/UGI7/_POWL_EAMWB_TYPE_ID	Type ID for AIW

Change View "View: Type definition": Details

New Entries Check

POWL Type ID /UGI7/_POWL_EAMWB_TYPE_ID

View: Type definition	
Description	Type ID for AIW
Feeder class	/UGI7/CL_MDG_EAM_WB_POWL_FEEDR
<input type="checkbox"/> Sync. call	
<input type="checkbox"/> No Msg. Wrapping	

3.5.8. Maintain POWL Type Role assignment

t-code: POWL_TYPER

Define visibility of worklist type at role level to make worklist type visible for user role or user group.

Application: /UGI7/_POWL_EAMWB_APPLID

POWL Type ID: /UGI7/_POWL_EAMWB_TYPE_ID

Description: Type Id for AIW.

Change View "View: Type - Role assignment": Overview

New Entries Check

Application	R.. POWL Type ID	Description
/UGI7/_POWL_EAMWB_APPLID	/UGI7/_POWL_EAMWB_TYPE_ID	Type ID for AIW

Change View "View: Type - Role assignment": Details

New Entries Check

Application	/UGI7/_POWL_EAMWB_APPLID
Role	
POWL Type ID	/UGI7/_POWL_EAMWB_TYPE_ID

View: Type - Role assignment	
Description	Type ID for AIW

3.6. Activate Services in SICF

To use the Asset WB and POWL Application, the following services need to be activated:

Path: /default_host/sap/bc/webdynpro/ugi7/

Run SICF T-code with above path and open the node by following the same path.

The services under ugi7 node need to be activated individually.

ugi	Namespace
ugi7	Namespace
• EAMWB_APP	Asset Information Workbench Application
• EAMWB_USMD_MOCR_CRE	Change Request
• MDG_EAMWB_POWL_INBX	MDG Asset Information Workbench POWL Inbox

Create/Change a Service

Path /default_host/sap/bc/webdynpro/ugi7/
 Service Name EAMWB_APP Service (Active)
 Lang. EN English Other Languages

Description 1	Asset Information Workbench Application
Description 2	
Description 3	

Service Data Logon Data Handler List Error Pages Administration

Service Options

Web Service
 Ignore inherited settings
 Load Balancing
 SAP Authoriz.
 Session Timeout 00:00:00 (HH:MM:SS)
 Compression Not specified

Interactive Options

GUI Interface Not specified GUI Configuration
 Support Accessibility Not specified

Create/Change a Service

Path /default_host/sap/bc/webdynpro/ugi7/
 Service Name M9D10042 Service (Active) Altern. Name: EAMWB_USMD_MO...
 Lang. EN English Other Languages

Description 1	Change Request
Description 2	
Description 3	

Service Data Logon Data Handler List Error Pages Administration

Service Options

Web Service
 Ignore inherited settings
 Load Balancing
 SAP Authoriz.
 Session Timeout 00:00:00 (HH:MM:SS)
 Compression Not specified

Interactive Options

GUI Interface Not specified GUI Configuration
 Support Accessibility Not specified

Create/Change a Service

Path /default_host/sap/bc/webdynpro/ugi7/
 Service Name WBC100101 Service (Active) Altern. Name: MDG_EAMWB_POW...
 Lang. EN English Other Languages

Description
 Description 1 MDG Asset Information Workbench POWL Inbox
 Description 2
 Description 3

Service Data Logon Data Handler List Error Pages Administration

Service Options
 Web Service
 Ignore inherited settings
 Load Balancing
 SAP Authoriz.
 Session Timeout 00:00:00 (HH:MM:SS)
 Compression Not specified

Interactive Options
 GUI Interface Not specified GUI Configuration
 Support Accessibility Not specified

3.7. Number Ranges

Refer UGI EAM 1909 Configuration Guide. It should be in place since EAM configuration should already be completed. Do check it only when you encounter any issue related to this section.


3.8. GenIL (Generic Interaction Layer) Component Adjustments

Refer UGI EAM 1909 Configuration Guide. It should be in place since EAM configuration should already be completed. Do check it only when you encounter any issue related to this section.

3.8.1. GenIL (Generic Interaction Layer) Component Adjustments

This section describes how to create GenIL enhancement in customer(Y/Z) namespace and save. Use the following steps to create the GenIL enhancement and save:

1. Execute transaction GENIL_MODEL_BROWSER
2. Create an enhancement with component /UGI/1 and the following details:
 - Prefix: optional
 - Enhancement class: /UGI7/CL_EAMWB_GENIL_ADAPTER
 - Component Enhancement class: /UGI/CL_MDG_EAM_GENIL_ADAPTER



- Save this enhancement and there are no additional steps are required.

Note

In case, a Z Customer Enhancement of the /UGI/1 GenIL component exist, then a Super Enhancement needs to be created to the current Existing Z Enhancement with the same settings above.

/ugi7/ enhancement needs to be a super enhancement of customer enhancement or vice versa.

3.9. Prerequisite Notes

Refer UGI EAM 1909 Configuration Guide. It should be in place since EAM configuration should already be completed. Do check it only when you encounter any issue related to this section.

3.9.1. Specific Prerequisite Notes

Refer UGI EAM 1909 Configuration Guide. It should be in place since EAM configuration should already be completed. Do check it only when you encounter any issue related to this section.

3.10. Prerequisite BC-Set activation


Refer UGI EAM 1909 Configuration Guide. It should be in place since EAM configuration should already be completed. Do check it only when you encounter any issue related to this section.

3.10.1. BC-Set for AIW

Activate () the following BC-Sets via t-code SCPR20.

If the activation does not occur with Default Mode, try with Expert Mode.

BC-Set ID	BC-Set Description
/UGI7/ASSETWB_CRTYPES (use Expert mode)	Change Request Types for AIW
Note: Ensure that the BC-Set /UGI7/ASSETWB_CRTYPES_02 needs to be activated after the activation of /UGI7/ASSETWB_CRTYPES. MDGAF_BCV may have already been activated by SAP domain or EAM 1909 configuration.	
/UGI7/ASSETWB_CRTYPES_02 (use Expert mode)	Change Request Type Configuration for AIW 2.0
/UGI7/ASSETWB_CRTYPES_300 (use Expert mode)	Change Request Type Configuration for AIW
/UGI7/ASSETWB_CRTYPES_1909	Change Request Type Configuration for AIW 1909
/UGI7/ASSETWB_HANDLER_ACTIVATION	Activate Handler Class for UGI enhancements
/UGI7/ASSETWB_POWL	BC-Set for POWL configurations

/UGI7/ASSETWB_POWL_DEL_300	Note: Before activating the BC-Set (/UGI7/ASSETWB_POWL_DEL_300), navigate to Utilities > User Settings > Maint. Transaction tab. Ensure that the field "Switch On" within Deletion Function is checked.	BC-Set to delete POWL configurations																																													
/UGI7/ASSETWB_REASON_REJREASONS		Reasons and Rejection Reasons for AIW																																													
/UGI7/ASSETWB_REASON_300		Reasons and Rejection Reasons for AIW																																													
/UGI7/ASSETWB_SERIAL_WORKITM_SEQ	Note: Run t-code /nmdgimg. Navigate to > Asset Information Workbench > Serial and Hybrid Workflow Steps Sequence > Choose AIWEAM0S. Delete all records.	Defining Work item approval sequence for AIW serial workflow																																													
/UGI7/ASSETWB_SERIAL_ITM_SEQ_300	Note: Run t-code /nmdgimg. Navigate to > Asset Information Workbench > Serial and Hybrid Workflow Steps Sequence > Choose AIWEAM0S. Check that there is only one record per entity. For example, there should be only one record for EQUI entity. In case, if there are more than one record per entity post activation of BC Set, the duplicate entries need to be deleted manually. Refer below screenshot for correct sequence.	Defining Workitem approval sequence for AIW release																																													
 <table border="1"> <thead> <tr> <th>Entity Type</th> <th>Sequence ...</th> <th>Description</th> </tr> </thead> <tbody> <tr><td>EQBOMHDR</td><td>7</td><td>EBOM - Equipment Bill of Material</td></tr> <tr><td>EQUI</td><td>4</td><td>EQUI - Equipment</td></tr> <tr><td>FLBOMHDR</td><td>6</td><td>FBOM - Functional Loc Bill of Material</td></tr> <tr><td>FUNCLOC</td><td>3</td><td>FLOC - Functional Location</td></tr> <tr><td>MPLAN</td><td>11</td><td>MPMI - Maintenance Plan</td></tr> <tr><td>MSPOINT</td><td>5</td><td>MSPT - Measuring Point</td></tr> <tr><td>OBJLINK</td><td>14</td><td>OBJL - Object Link</td></tr> <tr><td>OBJNINETWRK</td><td>13</td><td>OBJN - Object Network</td></tr> <tr><td>PMBOMHDR</td><td>2</td><td>MBOM - Material Bill of Material</td></tr> <tr><td>TLEQHDR</td><td>10</td><td>Equipment Task List</td></tr> <tr><td>TLFLHDR</td><td>9</td><td>Functional Location Task List</td></tr> <tr><td>TLGNHDR</td><td>8</td><td>General Task List</td></tr> <tr><td>WBSBOMHDR</td><td>12</td><td>WBOM - WBS Bill of Material</td></tr> <tr><td>WORKCNTR</td><td>1</td><td>WC - Work Center</td></tr> </tbody> </table>			Entity Type	Sequence ...	Description	EQBOMHDR	7	EBOM - Equipment Bill of Material	EQUI	4	EQUI - Equipment	FLBOMHDR	6	FBOM - Functional Loc Bill of Material	FUNCLOC	3	FLOC - Functional Location	MPLAN	11	MPMI - Maintenance Plan	MSPOINT	5	MSPT - Measuring Point	OBJLINK	14	OBJL - Object Link	OBJNINETWRK	13	OBJN - Object Network	PMBOMHDR	2	MBOM - Material Bill of Material	TLEQHDR	10	Equipment Task List	TLFLHDR	9	Functional Location Task List	TLGNHDR	8	General Task List	WBSBOMHDR	12	WBOM - WBS Bill of Material	WORKCNTR	1	WC - Work Center
Entity Type	Sequence ...	Description																																													
EQBOMHDR	7	EBOM - Equipment Bill of Material																																													
EQUI	4	EQUI - Equipment																																													
FLBOMHDR	6	FBOM - Functional Loc Bill of Material																																													
FUNCLOC	3	FLOC - Functional Location																																													
MPLAN	11	MPMI - Maintenance Plan																																													
MSPOINT	5	MSPT - Measuring Point																																													
OBJLINK	14	OBJL - Object Link																																													
OBJNINETWRK	13	OBJN - Object Network																																													
PMBOMHDR	2	MBOM - Material Bill of Material																																													
TLEQHDR	10	Equipment Task List																																													
TLFLHDR	9	Functional Location Task List																																													
TLGNHDR	8	General Task List																																													
WBSBOMHDR	12	WBOM - WBS Bill of Material																																													
WORKCNTR	1	WC - Work Center																																													
MDGAF_BCV		BCV Content for MDG Framework																																													
/UGI7_XOS_HDB_VIEWS_300	Note: Complete the steps in 3.10.4 BC-Set for Cross Entity HANA Search Views /UGI7_XOS_HDB_VIEWS_300 activation must be done before /UGI7/ASSETWB_XOS activation.	Hana Views for XOS AIW																																													
/UGI7/ASSETWB_XOS (Use Expert Mode)		Cross Search IDs for AIW																																													
/UGI7/ASSETWB_TL_MPACK_COMP_1909		Task List Package and Component detail in AIW 1909																																													

3.10.2. BC-Set for HANA Search

Refer UGI EAM 1909 Configuration Guide.

Below BC Sets need to be activated using t-code SCPR20.

/UGI7/ASSETWB_HDB_PP_FMAP_1909 - Field Mapping for HANA Search in AIW 1909

/UGI7/ASSETWB_HDB_SEARCH_1909 - Views Attribute for HANA Search in AIW 1909

3.10.3. BC-Set for AIW NON-LAM system

Below BC sets activation is mandatory, even if EAM 1909 system is configured with Non-LAM. This is required to avoid technical errors during execution in AIW.

Data Model BC sets:

- Run t-code SCPR20 and activate () BC-Set /UGI/MDG_EAM_LAM_USMD001.
- Run t-code SCPR20 and activate () BC-Set /UGI/MDG_EAM_DM_LAM_920.
- Run t-code SCPR20 and activate () BC-Set /UGI/MDG_EAM_DM_LAM_1909.

Data Model Structure BC sets:

- Run t-code SCPR20 and activate () BC-Set /UGI/MDG_EAM_LAM_USMD004.
 - Run t-code SCPR20 and activate () BC-Set /UGI/MDG_EAM_LAM_STRUCT_DM_920.


Note: Before activating the data model specific structure for LAM, ensure that the data model changes for LAM is activated.

For more details – Please refer UGI EAM 1909 Configuration guide (section 2.10->Point 4 and 2.10.2->Point3).

Note: Ignore this step if EAM 1909 is configured with LAM configuration.

3.10.4. BC-Set for Cross Entity HANA Search Views

To use cross-entity Search functionality, the following BC-Set /UGI7/_XOS_HDB_VIEWS_300 needs to be activated for importing the HANA search views.



After BC-Set activation, search views need to be generated using the following path.

T-Code MDGIMG > General Settings > Data Quality and Search > Search and Duplicate Check > Create Search View > Edit.

MDG Search View

 New	 	Search View	Description	Business Object Type	Status
 	/UGI7/EAM_AIW_EQ	AIW Equipment HANA Search	Individual Material	Generated	
 	/UGI7/EAM_AIW_EQBOM	AIW EQ BOM HANA Search	Individual Material Bill of Material	Generated	
 	/UGI7/EAM_AIW_EQTL	AIW Equipment Task List HANA Search	Equipment Task List	Generated	
 	/UGI7/EAM_AIW_FL	AIW Functional Location HANA Search	Installation Point	Generated	
 	/UGI7/EAM_AIW_FLBOM	AIW FLBOM HANA Search	Installation Point Bill of Material	Generated	
 	/UGI7/EAM_AIW_FLTL	AIW Functional Location Task List HANA Se...	Functional Location Task List	Generated	
 	/UGI7/EAM_AIW_GNTL	AIW General Task List HANA Search	General Task List	Generated	
 	/UGI7/EAM_AIW_MBOM	AIW MRO BOM HANA Search	Bill of Material	Generated	
 	/UGI7/EAM_AIW_MPMI	AIW Maintenance Plan HANA Search	Maintenance Plan	Generated	
 	/UGI7/EAM_AIW_MSP	AIW Measuring Point HANA Search	Measuring Device	Generated	
 	/UGI7/EAM_AIW_OBJLNK	AIW Object Link HANA Search	Object Link	Generated	
 	/UGI7/EAM_AIW_OBJNET	AIW Object Network HANA Search	Object Network	Generated	
 	/UGI7/EAM_AIW_WBSBOM	AIW WBS BOM HANA Search	WBS BoM	Generated	
 	/UGI7/EAM_AIW_WC	AIW Work Center HANA Search	Workcenter	Generated	

Enter the description and package name. Save and then generate.

Refer EAM 1909 Configuration guide for generating HANA views.

The following Search views needs to be generated.

- /UGI7/EAM_AIW_EQBOM
- /UGI7/EAM_AIW_EQ
- /UGI7/EAM_AIW_FLBOM
- /UGI7/EAM_AIW_FL
- /UGI7/EAM_AIW_MPMI
- /UGI7/EAM_AIW_MSP
- /UGI7/EAM_AIW_OBJLNK
- /UGI7/EAM_AIW_OBJNET
- /UGI7/EAM_AIW_MBOM
- /UGI7/EAM_AIW_EQTL
- /UGI7/EAM_AIW_FLTL
- /UGI7/EAM_AIW_GNTL
- /UGI7/EAM_AIW_WBSBOM
- /UGI7/EAM_AIW_WC

Use the following steps to Verify and uncheck DATBI_EIL field, this is to remove a duplicate field which can cause issues at runtime:

1. Run t-code /nmdgimg >General Settings > Data Quality and Search > Search and Duplicate Check > Create Search View.
2. Click on /UGI7/EAM_AIW_EQ.
3. Click on “Edit” button.
4. Click “Next” button.
5. Expand all and search for "DATBI_EIL - Valid To" and uncheck it (If it is already unchecked then kindly ignore step 5, 6 and 7).
6. Click “Next” button.
7. Save and Generate.

3.10.5. BC-Set for Cross Entity Search Configuration Entries

The BC-Set /UGI7/ASSETWB_XOS needs to be activated for using cross entity search.

Before activation, ensure that the following entries are in the location.

Run T-Code MDGIMG > General Settings > Data quality and Search > Search and duplicate check > Define search applications. Choose HA and select Allocation of entities.

Display View "Allocation of entities to Search Applications": Overview																															
 Dialog Structure Search Mode HA																															
Dialog Structure	Allocation of entities to Search Applications <table border="1"> <thead> <tr> <th>Data Model</th><th>Entity Type</th></tr> </thead> <tbody> <tr><td>U1</td><td>EQBOMHDR</td></tr> <tr><td>U1</td><td>EQUI</td></tr> <tr><td>U1</td><td>FLBOMHDR</td></tr> <tr><td>U1</td><td>FUNCLOC</td></tr> <tr><td>U1</td><td>MPLAN</td></tr> <tr><td>U1</td><td>MSPOINT</td></tr> <tr><td>U1</td><td>OBJLINK</td></tr> <tr><td>U1</td><td>OBJNETWRK</td></tr> <tr><td>U1</td><td>PMBOMHDR</td></tr> <tr><td>U1</td><td>TLEQHDR</td></tr> <tr><td>U1</td><td>TLFLHDR</td></tr> <tr><td>U1</td><td>TLGNHDR</td></tr> <tr><td>U1</td><td>WBSBOMHDR</td></tr> <tr><td>U1</td><td>WORKCNTR</td></tr> </tbody> </table>	Data Model	Entity Type	U1	EQBOMHDR	U1	EQUI	U1	FLBOMHDR	U1	FUNCLOC	U1	MPLAN	U1	MSPOINT	U1	OBJLINK	U1	OBJNETWRK	U1	PMBOMHDR	U1	TLEQHDR	U1	TLFLHDR	U1	TLGNHDR	U1	WBSBOMHDR	U1	WORKCNTR
Data Model	Entity Type																														
U1	EQBOMHDR																														
U1	EQUI																														
U1	FLBOMHDR																														
U1	FUNCLOC																														
U1	MPLAN																														
U1	MSPOINT																														
U1	OBJLINK																														
U1	OBJNETWRK																														
U1	PMBOMHDR																														
U1	TLEQHDR																														
U1	TLFLHDR																														
U1	TLGNHDR																														
U1	WBSBOMHDR																														
U1	WORKCNTR																														

If these entries exist, then proceed. If not, then check the EAM configuration again for EAM BC-Set /UGI/MDG_EAM_VC_DQ_SEARCH_920 activation.

Business Configuration Sets: Activation	
	
BC Set	/UGI7/ASSETWB_XOS
Short Text	Cross Search IDs for AIW

3.11. External API to handle MDG-AIW



3.12. Prerequisites and configuration for AIN Integration

Note: This is an optional step.

For enabling the AIN to S/4 integration, follow the pdf attachment and steps in “EAM-AIN Integration Function” UGI EAM 1909 Configuration Guide.

3.12.1. AIN Header Data Mapping

Refer UGI EAM 1909 Configuration Guide.

3.12.2. AIN Characteristics Value Mapping

Note: This is an optional step.

Refer UGI EAM 1909 Configuration Guide.

3.12.3. AIN FLP URL Parameter maintenance

Refer UGI EAM 1909 Configuration Guide.

3.13. Configuration for GEF Integration

Refer UGI EAM 1909 Configuration Guide.

In addition, the following business function needs to be activated (transaction SFW5) if customers would like to make use of the GEF Integration with AIW.

- Business Function /UGI7/AIW_GEF_920

4. Configuration Process

This section describes the minimal set of customizing steps and recommended check activities required to perform the following activities:

- For information on functional restrictions, see SAP Note: [2837674](#)

4.1. Activation check for Data Model U1

Data Model U1 should already be active. In case, if it is not active, activate and adjust U1 data model. For more information refer to UGI EAM 1909 Configuration Guide.

4.2. Navigate User Interface

- Link Log. Actions with UI Application and Bus. Act.: Standard Definition
- Link Logical Actions with Business Activity: Standard Definition

4.2.1. Link Log. Actions with UI Application and Bus. Act.: Standard Definition

Refer UGI EAM 1909 Configuration Guide.


Utopia has provided a report that can be leveraged to read the embedded Excel files here and update the configuration tables directly. The Logical actions with UI Application and Business Activity

configuration entries can also be entered or verified manually by opening the respective Excel file and copying to the SAP MDGIMG configuration.


Note

The Utopia report for uploading the configuration table entries does not provide an option to load directly into a transport. Saving the configuration entries into a transport can be achieved manually after the load by selecting Table View > Transport.

1. To run the report; run t-code SE38, then enter report /UGI3/MDG_UI_CONFIG_UPLOAD and execute or press F8.



2. Click on the file selection icon as indicated and navigate to where you stored the downloaded files from the relevant sections below for your implementation.



Note: For more information, see Customizing for Master Data Governance under > General Settings > Process Modeling > Business Activities > Link Log. Actions with UI Application and Bus. Act. Standard Definition.

4.2.1.1. AIW Specific Entries

Run the report as described in section [4.2.1](#) above, using the Excel file below.



Verify Customizing in Master Data Governance under > General Settings > Process Modeling > Business Activities > Link Log. Actions with UI Application and Bus. Act. Standard Definition

4.2.2. Link Logical Actions with Business Activity: Standard Definition

Refer UGI EAM 1909 Configuration Guide.

4.3. Verify UI Modeling (Optional)

UI configuration activities are relevant only if you want to change the UI, or if the U1 data model has been enhanced.

In this customizing activity, you can specify if and where the system hides the entity types for the data model U1.

Verify the pre-delivered field properties for the data model U1 in Customizing under > General Settings > UI Modeling > Define Field Properties for UI.

The Web Dynpro application and the application configuration in the PFCG role combine with settings made in Customizing to determine the UI displayed.

You must verify the UI modeling for the data model U1 and the following Web Dynpro applications and related configurations:

Application	Application Configuration	UI Configuration
/UGI7/EAMWB/APP	/UGI7/EAMWB/APP	/UGI7/EAMWB_OVP_COMP

4.4. Set up of Data Replication

4.4.1. Customizing for Data Replication Framework (DRF- AIW Specific)

Refer EAM 1909 Configuration Guide. It should be in place since EAM configuration should already be completed. Do check it only when you encounter any issue related to this section.

The following additional setting on sequencing is required to support Hierarchy replication for AIW:

1. Enter transaction DRFIMG.
2. Navigate to > Data Replication > Define Custom Settings for Data Replication > Define Replication Models.
3. Select Replication model and click on Assign Outbound Implementation.
4. Update the Sequence for respective outbound Implementation as per the following table.

SI No.	Outbound Implementation	Sequence
1	/UGI/WRKCN	10
2	/UGI/MBOM	11
3	/UGI/I_FL	12
4	/UGI/I_EM	13
5	/UGI/I_MSP	14
6	/UGI/FLBOM	15
7	/UGI/EQBOM	16
8	/UGI/I_TL	17
9	/UGI/I_TLF	18
10	/UGI/I_TLE	19

11	/UGI/I_MP	20
12	/UGI/WBBOM	21
13	/UGI/I_ON	22
14	/UGI/I_DL	23

4.5. Set Up Search

Refer UGI EAM 1909 Configuration Guide. It should be in place since EAM configuration should already be completed. Do check it only when you encounter any issue related to this section.

4.5.1. Create the Search View

Refer UGI EAM 1909 Configuration Guide. It should be in place since EAM configuration should already be completed. Do check it only when you encounter any issue related to this section.

4.6. Verify Data Quality, Search Settings, and Duplicate Check

Refer UGI EAM 1909 Configuration Guide. It should be in place since EAM configuration should already be completed. Do check it only when you encounter any issue related to this section.

For Cross Search Application feature, generate the HANA views coming as part of BC-Set activation in [3.10.3 section](#) (BC-Set /UGI7/_XOS_HDB_VIEWS_300)

Note:

EAM HANA Search view generation should happen smoothly, this can be used as an indication of smoothness of AIW Cross Search configuration; this is because AIW Cross Search HANA views generation uses same framework which EAM uses for generation.

4.6.1. Configuration of the duplicate check for HANA search

Refer UGI EAM 1909 Configuration Guide. It should be in place since EAM configuration should already be completed. Do check it only when you encounter any issue related to this section.

4.7. Verify Remaining Process Modeling Settings

Refer UGI EAM 1909 Configuration Guide. It should be in place since EAM configuration should already be completed. Do check it only when you encounter any issue related to this section.

4.7.1. Mixed Multi-Object Change Request (MOCR)

To proceed further, verify that the business activity (UAIW) is configured in your system and that they are assigned to the default data model U1.

4.7.1.1. UAIW Asset Information Workbench

For more information, see Customizing for Master Data Governance under > General Settings > Process Modeling > Business Activities > Create Business Activity.

Create new Change Request types for data model U1 or validate after import using business configuration sets (BC-Sets).

For more information, see Customizing for Master Data Governance under > General Settings > Process Modeling > Change Requests > Create Change Request Type.

The following table displays the proposed change request types for data model U1. Only the relevant columns are included.

Change Request Type	Data Model	Description	Single Object	Main Entity Type	Workflow
AIWEAM0P	U1	Asset Information Workbench Parallel	No	<leave empty>	WS80000007
AIWEAM0S	U1	Asset Information Workbench Serial	No	<leave empty>	WS80000010
AIWEAMHY	U1	Asset Information Workbench Hybrid	No	<leave empty>	WS80000013

The MOCR is a special workflow process in AIW wherein more than one “Type 1” entity of different technical object is encompassed within same change request. Here, each technical object (grouped under same type) is routed to different approver group. This is possible using Business Rule Framework (BRF+) configurations.

The following settings should exist in the Entity Types, subfolder of the Change Request types:

Entity Type	Scenario	Configuration ID	Optional	Message Output
DRADEQBOM	<leave empty>	<leave empty>	No	Standard
DRADEQUI	<leave empty>	<leave empty>	No	Standard
DRADFLBOM	<leave empty>	<leave empty>	No	Standard
DRADFLOC	<leave empty>	<leave empty>	No	Standard
DRADMBOM	<leave empty>	<leave empty>	No	Standard
DRADMSPT	<leave empty>	<leave empty>	No	Standard
DRADOL	<leave empty>	<leave empty>	No	Standard
DRADTLEQ	<leave empty>	<leave empty>	No	Standard
DRADTLFL	<leave empty>	<leave empty>	No	Standard
DRADTLGN	<leave empty>	<leave empty>	No	Standard
DRADWBOM	<leave empty>	<leave empty>	No	Standard
EQBOMHDR	<leave empty>	<leave empty>	No	Standard
EQUI	<leave empty>	<leave empty>	No	Standard
EQUIADDRN	<leave empty>	<leave empty>	No	Standard
FLBOMHDR	<leave empty>	<leave empty>	No	Standard
FUNCLOC	<leave empty>	<leave empty>	No	Standard
FUNCLOCAN	<leave empty>	<leave empty>	No	Standard

MPLAN	<leave empty>	<leave empty>	No	Standard
MSPOINT	<leave empty>	<leave empty>	No	Standard
OBJLINK	<leave empty>	<leave empty>	No	Standard
OBJNETWRK	<leave empty>	<leave empty>	No	Standard
PMBOMHDR	<leave empty>	<leave empty>	No	Standard
TLEQHDR	<leave empty>	<leave empty>	No	Standard
TLFLHDR	<leave empty>	<leave empty>	No	Standard
TLGNHDR	<leave empty>	<leave empty>	No	Standard
WBSBOMHDR	<leave empty>	<leave empty>	No	Standard
WORKCNTR	<leave empty>	<leave empty>	No	Standard

To the Change Request type, add the following Business Activity:

Business Activity	Description
UAIW	Asset Information Workbench

4.8. Configuration Change Request Settings

Refer UGI EAM 1909 Configuration Guide. It should be in place since EAM configuration should already be completed. Do check it only when you encounter any issue related to this section.

4.8.1. Configuration Variant Splitter

Refer UGI EAM 1909 Configuration Guide. It should be in place since EAM configuration should already be completed. Do check it only when you encounter any issue related to this section.

4.9. Configure Workflow Tasks

There are two types of Change Requests with the following approval types:

- Serial Approval
- Parallel approval

4.9.1. AIW Parallel/Serial Workflow Process flow (4 step BRF+)

- Parallel workflow: You can configure parallel workflow to approve work items without specific order Workflow template “WS80000007” is assigned to the MOCR parallel Change Request type “AIWEAM0P”.
- Serial Workflow: You can configure Serial workflow to approve work item in specific pre-defined order. Workflow template “WS80000010” is assigned to the MOCR serial Change Request Type “AIWEAM0S”.
- Hybrid Workflow: You can configure Hybrid workflow to approve work item in hybrid pre-defined order. Workflow template “WS80000013” is assigned to the MOCR serial Change Request Type “AIWEAMHY”.

Both parallel workflow and serial workflow can be used. It is recommended that you copy the delivered Change Request types according to your own naming conventions and keep the Utopia-delivered CR types as reference.

4.9.1.1. Link Change Request type to Workflow Template

Customizing activity using transaction path MDGIMG > General Settings > Process Modeling > Change Requests > Create Change Request Type.

Workflow template “WS80000007” is assigned to the parallel MOCR Change Request type and Workflow template “WS80000010” for serial MOCR change request type as displayed in the following screen.

Workflow template “WS80000013” for Hybrid MOCR change request type as displayed in the following screen.

Type of Change Request										
Type of Chg. Request	Edition Type	Data Model	Description (medium text)	Objects Re...	Single Obj...	Parallel	Main Entity Type	Workflow	Ts	
AIWEAMOP	U1	Asset Information Workbench Parallel						WS80000007		
AIWEAMOS	U1	Asset Information Workbench Serial						WS80000010		
AIWEAMHY	U1	Asset Information Workbench Hybrid						WS80000013		

4.9.1.2. Workflow Step Numbers

Customizing activity using transaction path MDGIMG > General Settings > Process Modeling > Workflow > Rule-Based Workflow > Define Change Request Steps for Rule-Based Workflow.

For 2,3 or 4 step BRF+ controlled MOCR workflow separate CR steps need to be defined for each technical object in AIW.

The following table displays a list of workflow step numbers defined for Change Request type “AIWEAMOP”.

You can use same set of entries defined in the following table for CR type “AIWEAMOS” and “AIWEAMHY” also.

Type of CR	CR Step	Key	Validation	Description
AIWEAMOP	00			Processing
AIWEAMOP	20			Equipment Revision Processing
AIWEAMOP	21			Functional Location Revision Processing
AIWEAMOP	22			Measuring Points Revision Processing
AIWEAMOP	23			Work Center Revision Processing
AIWEAMOP	24			Maintenance Plan Revision Processing
AIWEAMOP	25			General Task List Revision Processing
AIWEAMOP	26			Func. Loc. Task List Revision Processing
AIWEAMOP	27			Equipment Task List Revision Processing
AIWEAMOP	28			Material BOM Revision Processing
AIWEAMOP	29			Object Links Revision Processing
AIWEAMOP	30			Networks Revision Processing
AIWEAMOP	31			WBS BOM Revision Processing
AIWEAMOP	32			Functional Location BOM Revision Processing
AIWEAMOP	33			Equipment BOM Revision Processing
AIWEAMOP	40			Equipment Specialist
AIWEAMOP	41			Functional Location Specialist
AIWEAMOP	42			Measuring Points Specialist
AIWEAMOP	43			Work Center Specialist
AIWEAMOP	44			Maintenance Plan Specialist
AIWEAMOP	45			General Task List Specialist
AIWEAMOP	46			Func. Loc. Task List Specialist
AIWEAMOP	47			Equipment Task List Specialist

AIWEAM0P	48		Material BOM Specialist
AIWEAM0P	51		WBS BOM Specialist
AIWEAM0P	52		Functional Location BOM Specialist
AIWEAM0P	53		Equipment BOM Specialist
AIWEAM0P	60		Equipment Stewart
AIWEAM0P	61		Functional Location Stewart
AIWEAM0P	62		Measuring Points Stewart
AIWEAM0P	63		Work Center Stewart
AIWEAM0P	64		Maintenance Plan Stewart
AIWEAM0P	65		General Task List Stewart
AIWEAM0P	66		Func. Loc. Task List Stewart
AIWEAM0P	67		Equipment Task List Stewart
AIWEAM0P	68		Material BOM Stewart
AIWEAM0P	71		WBS BOM Stewart
AIWEAM0P	72		Functional Location BOM Stewart
AIWEAM0P	73		Equipment BOM Stewart
AIWEAM0P	80		Final Check
AIWEAM0P	91		Activation
AIWEAM0P	92		Withdraw
AIWEAM0P	93		Validation
AIWEAM0P	95		Revision Processing
AIWEAM0P	99		Complete


4.9.1.3. Change Request Actions (MOCR Specific)

Using MOCR specific action Activate and Launch New MOCR you can activate current MOCR and using same MOCR data it will create one new CR.

Customizing activity using transaction path MDGIMG > General Settings > Process Modeling > Workflow > Define Change Request Actions.

AIW specific Custom Action "U1" is defined to handle "Activate & Launch New MOCR" functionality of the workflow process.

Change View "Edit Actions": Details



Action	U1
Description	Activate and Launch New MOCR
Pushbutton Text	Activate and Launch New MOCR
Quick Info Text	Activate and Launch New MOCR
<input type="checkbox"/> Check Required	
<input type="checkbox"/> Note Required	
<input type="checkbox"/> Reason for Rejection	


Note

Reason for rejection should not be enabled for this step, as this step performs activating the current Change Request and launching new MOCR only. No rejection option is provided for this step.

4.9.1.4. Change Request Step Types and Assign Actions (MOCR Specific)

Customizing activity using transaction path MDGIMG > General Settings > Process Modeling > Workflow > Define Change Request Step Types and Assign Actions.

This configuration defines the buttons displayed in the UI during workflow approval process when step-type "U" is configured in BRF+.




Change View "Step Types": Details

New Entries Back Forward Print Close

Dialog Structure Step Type **U**

- Step Types
 - Assign Actions

Step Types	
Description	Activate and Launch New MOCR
Window Title	Activate and Launch New MOCR



Change View "Assign Actions": Overview

New Entries Back Forward Print Close

Dialog Structure Step Type **U**

- Step Types
 - Assign Actions

Action	Description	Sequence
09	Activate	1
10	Send for Revision	3
U1	Activate and Launch New MOCR	2

4.10. Set Up the Rule-Based Workflow

MOCR is designed to use only BRF+ controlled workflow to determine next approver, workflow step, assign CR status and execute background actions.

The standard MDG framework offers BRF+ application that can be configured for each change request type from the following menu path (MDGIMG).

Customizing activity using transaction path MDGIMG > General Settings > Process Modeling > Workflow > Rule-Based Workflow > Configure Rule-Based Workflow.

This will launch the Process Definition of Rule-Based Workflow in web browser. The following configuration is applicable for both Parallel and Serial workflow. We have captured the steps for parallel workflow only. Same steps should be repeated for Serial and Hybrid workflow.

4.10.1. Configure Rule-Based Workflow

Use the following steps to configure rule-based workflow:

1. Launch the application and enter the Change Request type "AIWEAM0P" and click "Continue" button.

Process Definition of Rule-Based Workflow

 Continue

* Type of Change Request: **AIWEAMOP**  Asset Information Workbench Parallel

In case of Serial Workflow, enter the Change Request type as displayed in the following screen and follow the same process.

Process Definition of Rule-Based Workflow

 Continue

* Type of Change Request: **AIWEAMOS**  Asset Information Workbench Serial

In case of Hybrid Workflow, enter the Change Request type as displayed in the following screen and follow the same process.

Process Definition of Rule-Based Workflow

 Continue

* Type of Change Request: **AIWEAMHY**  Asset Information Workbench Hybrid

If system asks for software component explicitly in the Transport request popup, enter UGI7.

The Business Rule Framework Plus screen is displayed.

To route Change Request objects based on the “Entity Type” (Type 1) within a CR, the “Entity type” field should be included as a parameter to the BRF+ function, use the following steps:

2. Expand the Trigger Function from the Catalog Structure on the left pane and double-click on “Function to Call” Ruleset as displayed in the screen.

Function: USMD_FN_CALL_DT_RS, Call Decision Table Ruleset

Back | Edit | Check | Save | Activate | Delete | More

General

Detail

Simulation

Mode: Event Mode

Signature Assigned Rulesets

Context

Component Name	Type
CR_PRIORITY	Chng. Req. Priority
CR_REASON	Chng. Req. Reason
CR_REASON_REJ	CR Rejection Reason
CR_TYPE	Chng. Req. Type
PARENT_STEP	CR Parent Step
PAR_AGT_GRP_NUM	Parallel Agt Grp No.
PREVIOUS_ACTION	Previous Action
PREVIOUS_STEP	CR Previous Step
S_SINGLE_VALUE	Cond. Result Header
T NON USER AGENT GROUP	Non-User Agent Group

3. Click on the “Edit” button on the toolbar.
4. Click on “Add New Data Object” button.
5. Choose the option “Add New Data Object” from drop-down list.
The Create Object dialog box is displayed.
6. Select “Element” from the drop-down list.
7. Enter Name as “USMD_ENTITY” and select the Binding Type as “Bind to DDIC Element” from the drop-down list and click Create and Navigate to Object as displayed in the following screen.

Create Object

General data

Type: Element
 * Name: USMD_ENTITY
 Short Text:
 Text:
 Application: USMD_003N7K826NGCBUUTOV4UF1729

Element

Properties

Define Data Binding

Binding Type: No Binding
 Define Element
 Element Type:

No Binding
 Bind to DDIC element (Data Dictionary)
 Bind to existing BRFplus element
 No Binding

Element Attributes

Length: 255

Create And Navigate To Object

8. Enter DDIC Element “USMD_ENTITY” and click “OK”.

Bind DDIC

DDIC Element: **USMD_ENTITY**

Create Object

General data

Type:	Element
* Name:	USMD_ENTITY
Short Text:	Entity Type
Text:	Entity Type
Application:	USMD_006E12SCXDTEFZDFLSM8PSUU8

Element

Properties													
Value Help													
Define Data Binding <table border="1"> <tr><td>Binding Type:</td><td>Bind to DD</td></tr> <tr><td>DDIC Element:</td><td>USMD_ENTIT</td></tr> <tr><td>DDIC Descri...:</td><td>Entity Type</td></tr> </table> Element Attributes <table border="1"> <tr><td>Length:</td><td>9</td></tr> <tr><td>Convert to U...:</td><td><input checked="" type="checkbox"/></td></tr> <tr><td>Numeric Co...:</td><td></td></tr> </table>		Binding Type:	Bind to DD	DDIC Element:	USMD_ENTIT	DDIC Descri...:	Entity Type	Length:	9	Convert to U...:	<input checked="" type="checkbox"/>	Numeric Co...:	
Binding Type:	Bind to DD												
DDIC Element:	USMD_ENTIT												
DDIC Descri...:	Entity Type												
Length:	9												
Convert to U...:	<input checked="" type="checkbox"/>												
Numeric Co...:													
Define Element Properties <table border="1"> <tr><td>Element Type:</td><td>Text</td></tr> </table>		Element Type:	Text										
Element Type:	Text												
<input type="button" value="Create"/> <input type="button" value="Create And Navigate To Object"/> <input type="button" value="Cancel"/>													

9. Click “Create and Navigate To Object” button.

The following screen displays the details of parameter “USMD_ENTITY” and it is being part of the BRF+ function interface. This screen displays the technical details of the added parameter.

Element (Text): USMD_ENTITY, Entity type

General

Name:	USMD_ENTITY
ID:	000C2933CE461ED785E2B76D3DF4E10A
Access Level:	Application
Storage Type:	Customizing Transportable

Detail

Properties	Domain Values	Additional Properties
Define Data Binding Binding Type: Bind to DDIC element (Da) Refresh Binding DDIC Element: USMD_ENTITY Where-Used List DDIC Description: Entity Type		
Element Attributes Length: <input type="text" value="9"/> Convert to Uppercase: <input checked="" type="checkbox"/>		
Define Element Properties Element Type: Text Allowed Comparisons: No Restriction		

10. Save and activate the new element.

The added parameter in the Function “Call Ruleset” screen is displayed.

Function: USMD_FN_CALL_DT_RS, Call Decision Table Ruleset

Back | Edit | Check | Save | Activate | Delete | More

General

Detail

Simulation

Mode: Event Mode

Signature Assigned Rulesets

Context

Component Name	Type
CR_REASON_REJ	Element (Text)
CR_TYPE	Element (Text)
PARENT_STEP	Element (Text)
PAR_AGT_GRP_NUM	Element (Text)
PREVIOUS_ACTION	Element (Text)
PREVIOUS_STEP	Element (Text)
S_SINGLE_VALUE	Structure
T_NON_USER_AGENT_GROUP	Table
T_USER_AGENT_GROUP	Table
USMD_ENTITY	Element (Text)

The AIW workflow uses the following decision tables for Rule-Based Workflow:

- Single Value Decision Table
- User Agent Decision Table
- Non-User Agent Decision Table

11. Single Value Decision Table


This is the master workflow table. This table lists the workflow steps and references the other two tables when necessary.

Single value decision table gets executed first from the BRF+ function to determine the next CR step and CR status based on the current step and action. The screenshot of BRF+ rules configured for Step 4 workflow approval process is displayed below.

Important: Before configuring the single value decision table, the field “USMD_ENTITY” defined in previous step is included as one of the mandatory decision parameters.


Use the following steps to include the field “USMD_ENTITY” as a mandatory decision parameter:

- Expand Decision tables and double-click on Single Value Decision table.
 - Switch to Edit mode.
 - Click “Table Settings” button from the Table Contents.
- The Table Settings dialog box is displayed.
- Add the USMD_ENTITY parameter “Entity Type” to the Condition Columns via “insert column” “From context data objects” and move it to the first row within the list of columns.
 - Deselect the “Action” checkbox that is selected by default (applicable to only 1909).
 - Save and activate those settings.



This screenshot shows the SAP Business Rule Framework plus interface. The left sidebar shows a tree structure under 'Catalog Structure' for 'USMD_SSW_CATA_AI'. Under 'Decision Tables', three items are listed: 'Non-User Agent', 'User Agent Det', and 'Single Value Di'. The 'Single Value Di' item is currently selected, highlighted with a blue background. The main panel displays the 'Decision Table: DT_SINGLE_VAL_AIWEAMOP' settings. The 'General' tab is active. Below it, the 'Detail' tab is shown with buttons for 'Additional Actions', 'Context Overview', and 'Start Simulation'. The 'Table Contents' tab is also visible, showing a table with columns for 'CR Previous Step', 'Previous Action', 'Chng. Req. Priority', 'Chng. Req. Reason', and 'CR Rejection Reason'. A message at the bottom of the table area states: 'Table contains no rows. Use "Insert New Row" to add conditions.'

Table Settings



This screenshot shows the 'Table Settings' dialog box. At the top, it says 'Result Data Object: ... Cond. Result Header ...'. The 'Table Check Settings' section contains two dropdown menus: 'Overlap Check Settings' set to 'Application Default' and 'Completeness Check Settings' also set to 'Application Default'. The 'List of Columns' section is divided into two tabs: 'Condition Columns' and 'Result Columns'. The 'Condition Columns' tab shows a table with columns: 'From Context Data Objects...', 'Text', 'Optional for Processing', 'Mandatory Input', and 'Column Accessibility'. Several rows are listed, including 'CR Previous Step', 'Previous Action', 'Chng. Req. Priority', 'Chng. Req. Reason', 'CR Rejection Reason', 'CR Parent Step', and 'Parallel Agt Grp No.'. The 'Result Columns' tab shows a similar table structure with columns: 'Column Name', 'Text', 'Action Column', 'Mandatory Input', and 'Column Accessibility'. Rows listed include 'COND_ALIAS', 'NEW_STEP', 'NEW_CR_STATUS', 'EXP_COMPLET...', 'MERGE_TYPE', 'MERGE_PARAM', and 'DYNAMIC_AGT...'. The 'Column Accessibility' column for most rows shows 'Full Access (Cha...)'.

Context Query[Hide Search Fields](#)**Search Criteria**

Element Type	is equal to	Any	+
Name	is equal to	*	+ -
Text	is equal to	*	+ -

Maximum Number of Results: 200

[Search](#) [Clear](#) [Reset](#)

Result list: 27 objects found

Previous Next Show All Objects Where Used				
	Object	Status	Type	Application
	Hours to Completion	■	Number	RBWF Main Appl.
	Merge Parameter	■	Text	RBWF Main Appl.
	Merge Type	■	Text	RBWF Main Appl.
	New CR Status	■	Text	RBWF Main Appl.
	New Chng. Req. Step	■	Text	RBWF Main Appl.
	Entity Type	■	Text	RBWF_APP_AIWEAM0P
▼	Non-User Agent Group	■	Structure	RBWF Main Appl.
	Agent Group	■	Text	RBWF Main Appl.
	Process Pattern	■	Text	RBWF Main Appl.
	Service Name	■	Text	RBWF Main Appl.

Table Settings**Result Data Object**

- Settings:
- Return all matches found
 - Return initial value if no match is found
 - Return Exception for partial match

Result Data Object: [Cond. Result Header](#)**Table Check Settings**

- Overlap Check Settings: [Application Default](#)
- Completeness Check Settings: [Application Default](#)

List of Columns**Condition Columns**

	Column Name	Text	Optional for Processing	Mandatory Input	Column Accessibility
■	USMD_ENTITY	Entity Type	<input type="checkbox"/>	<input checked="" type="checkbox"/>	Full Access (Cha... ▾
■	PREVIOUS_STEP	CR Previous Step	<input type="checkbox"/>	<input checked="" type="checkbox"/>	Full Access (Cha... ▾
■	PREVIOUS_AC...	Previous Action	<input type="checkbox"/>	<input type="checkbox"/>	Full Access (Cha... ▾
■	CR_PRIORITY	Chng. Req. Priority	<input checked="" type="checkbox"/>	<input type="checkbox"/>	Full Access (Cha... ▾
■	CR_REASON	Chng. Req. Reason	<input checked="" type="checkbox"/>	<input type="checkbox"/>	Full Access (Cha... ▾
■	CR_REASON_REJ	CR Rejection Reason	<input checked="" type="checkbox"/>	<input type="checkbox"/>	Full Access (Cha... ▾
■	PARENT_STEP	CR Parent Step	<input checked="" type="checkbox"/>	<input type="checkbox"/>	Full Access (Cha... ▾

[OK](#)[Cancel](#)

Click Ok after moving USMD_ENTITY to the top as first column.

Now import the data from the excel (attached below or see  Note below) to this table.

Detail

Additional Actions	Context Overview	Start Simulation
Check Completeness Check Overlaps Rearrange... Merge Rows Import From Excel Export To Excel		
Find: <input type="text"/> Next Previous		
CR Previous Step Previous Action		Chng. Req. Priority

No rows. Use "Insert New Row" to add conditions.

After upload, The Table Contents are displayed. Save and activate.

Table Contents

Find:	CR Previous Step	Previous Action	Chng. Req. Prio...	Chng. Req. Rea...
USMD_ENTITY	=00 (Processing)			
=EQUI (EQUI - Equipment)	=00 (Processing)			
=FUNCLOC (FLOC - Functional Location)	=00 (Processing)			
=MSPOINT (MSPT - Measuring Point)	=00 (Processing)			
=WORKCNTR (WC - Work Center)	=00 (Processing)			
=MPLAN (MPMI - Maintenance Plan)	=00 (Processing)			
=TLGNHDR (General Task List)	=00 (Processing)			
=TLFLHDR (Functional Location Task List)	=00 (Processing)			
=TLEQHDR (Equipment Task List)	=00 (Processing)			
=PMBOMHDR (MBOM - Bill of Material)	=00 (Processing)			
=OBJLINK (OBJL - Object Link)	=00 (Processing)			
=OBJNETWRK (OBJN - Object Network)	=00 (Processing)			
=EQUI (EQUI - Equipment)	=40 (Equipment Specialist)	=03 (Approve)		
=EQUI (EQUI - Equipment)	=40 (Equipment Specialist)	=04 (Reject)		
=FUNCLOC (FLOC - Functional Location)	=41 (Functional Location Specialist)	=03 (Approve)		
=FUNCLOC (FLOC - Functional Location)	=41 (Functional Location Specialist)	=04 (Reject)		



i Note

Download the attached Excel file from the link [AIW Help Portal](#) on Utopia's website.

12. User Agent Decision Table

This decision table contains a list of user assignments to workflow tasks.

The BRF+ application feeds the results of single value decision table to user agent table. If the next change request step is dialog (user action required), then the next approver is determined based on the value of condition alias in single value decision table. The dialog user could be an SAP user/Position/Role etc.

The following screen displays the user agent decision table maintained for 4 step BRF+ WF.

Table Contents				
Condition Alias	User Agt Grp No.	Step Type	User Agent Type	User Agent Value
=3	001	4 (Revise Change Request)	SU (Special User (Initiator/Last-Step))	INIT
=40	001	2 (Approve Change Request)	AG (Role)	/UGI7/AIW_SPEC_EQUI
=41	001	2 (Approve Change Request)	AG (Role)	/UGI7/AIW_SPEC_FUNCLOC
=42	001	2 (Approve Change Request)	AG (Role)	/UGI7/AIW_SPEC_MSPOINT
=43	001	2 (Approve Change Request)	AG (Role)	/UGI7/AIW_SPEC_WORKCNTR
=44	001	2 (Approve Change Request)	AG (Role)	/UGI7/AIW_SPEC_MPLAN
=45	001	2 (Approve Change Request)	AG (Role)	/UGI7/AIW_SPEC_TLGNHDR
=46	001	2 (Approve Change Request)	AG (Role)	/UGI7/AIW_SPEC_TLFLHDR
=47	001	2 (Approve Change Request)	AG (Role)	/UGI7/AIW_SPEC_TLEQHDR
=48	001	2 (Approve Change Request)	AG (Role)	/UGI7/AIW_SPEC_PMBOMHDR
=49	001	2 (Approve Change Request)	AG (Role)	/UGI7/AIW_SPEC_OBJLINK
=50	001	2 (Approve Change Request)	AG (Role)	/UGI7/AIW_SPEC_OBJNETWRK
=11	001	U (Activate & Launch New MOCR)	AG (Role)	/UGI7/AIW_STEW

 DT_USER_AGT_GRP_AIWEAM0P.XLSX
  DT_USER_AGT_GRP_AIWEAM0S.XLSX
  DT_USER_AGT_GRP_AIWEAMHY.xls

Note

Download the attached Excel file from the link [AIW Help Portal](#) on Utopia's website.

13. Non-User Agent Decision Table

This decision table contains a list of system tasks.

The results of Single Value Decision Table are passed to the Non-User Agent Decision Table to determine the background step details of the next workflow step.

The following screen displays the decision table set up for change request type "AIWEAM0P".

Table Contents			
Condition Alias	Agent Group	Process Pattern	Service Name
=2	001	06 (Activation (Bypass Snapshot))	
=6	001	99 (Complete (Sub-)Workflow)	
=8	001	08 (Roll Back Change Request)	


 DT_NON_USER_AGT_GRP_AIWEAM0P.xls
  DT_NON_USER_AGT_GRP_AIWEAM0S.xls
  DT_NON_USER_AGT_GRP_AIWEAMHY.xls

Note

Download the attached Excel file from the link [AIW Help Portal](#) on Utopia's website.

Note

Ensure that Green Indicator is there. Close and reopen the screen again to ensure that it's done.



4.11. Choose where you want to run SAP MDG

You can run SAP Master Data Governance in either of the following environments:

- SAP NetWeaver Portal
- SAP NetWeaver Business Client

4.11.1. SAP NetWeaver Portal

Refer UGI EAM 1909 Configuration Guide. It should be in place since EAM configuration should already be completed. Do check it only when you encounter any issue related to this section.

4.11.2. SAP NetWeaver Business Client

If you are running SAP Master Data Governance on the SAP NetWeaver Business Client (and not on the SAP NetWeaver Portal), you need to create, define, and configure the roles for the Business Client in the SAP ERP system. The role /UGI7/AIW_REQ needs to be created using the t-code PFCG. This role contains all authorizations needed to create and follow up change requests for AIW.

4.12. Configure Process Quality Metrics (Optional)

For the priorities, reasons, or rejection reasons for change requests, there are example values available via BC-Set activation.

To start, choose Activate and maintain the default settings.

The codes can be used later for change request analytics (process quality analysis). They also can be used to influence the workflow-driven processes. For example, depending on the priority of a change request, you can mark it for special processing.

To update any of the Process Quality Metrics (PQM), perform the following activity in Customizing for Master Data Governance under ► General Settings ► Process Modeling ► Change Requests ► Define Priorities/Reasons/Rejection Reasons for Change Requests.

4.12.1. Change Request Priorities

Priority	Description
1	High Priority
2	Medium Priority
3	Low Priority

4.12.2. Change Request Reasons

Type of Change Request	Reason	Description
AIWEAM0P	01	Process Multiple EAM Masters
AIWEAM0S	01	Process Multiple EAM Masters
AIWEAMHY	01	Process Multiple EAM Masters

4.12.3. Change Request Rejections

Type of Change Request	Reason for Rejection	Description
AIWEAM0P	01	Incomplete information
AIWEAM0P	02	Does not suit business requirements
AIWEAM0P	03	No proper Justification

Type of Change Request	Reason for Rejection	Description
AIWEAMHY	01	Incomplete information
AIWEAMHY	02	Does not suit business requirements
AIWEAMHY	03	No proper Justification

Type of Change Request	Reason for Rejection	Description
AIWEAM0S	01	Incomplete information
AIWEAM0S	02	Does not suit business requirements
AIWEAM0S	03	No proper Justification

4.13. Workflow Templates for SAP Asset Information Workbench by Utopia


AIW is delivered with two possible workflow scenarios (Parallel and Serial). This section describes about the parallel workflow approval process of AIW. Two custom workflow templates are created for this scenario and the following section provides detailed description.

4.13.1. WS80000007 – Multi-Object Change Request WF

This workflow template consists of the following steps:


1. Start workflow
The MOCR workflow is started when a user submits a MOCR.
2. Get Change Request Type

This background tasks determines the Change Request type based on the Change Request number by executing the class method "GET_CR_TYPE" of class "CL_USMD_WF_SSW". The following screen is the binding between task and workflow container. Standard Task "TS60807944" is used at this workflow step "000334".




3. Get TYPE 1 Entities

This background step retrieves all type 1 entities in MOCR into workflow container. This is done by executing the method "GET_CREQUEST_ENTITIES" of class "/UGIT/USMD_WF_SSW". Custom task "TS80000008" (step 000235) is created for this purpose. The following screen displays the binding between task and workflow container.




4. Generate object instance using key

This background step creates one instance of business object "BUS2250" for each type 1 entity group determined in step (b) above and updates the workflow container. This is achieved by creating parallel instance for each entry in workflow container "CREQUEST_GROUP" and calling the method "GENERICINSTANTIATE" of business object "SYSTEM" of the standard task "TS01200205" (step 000240). The following screen is the binding between task and workflow container.




5. MDG BRF+ (Parallel processing of Technical objects in MOCR)

This step calls the workflow 80000008(step 000231) as sub-workflow for each type 1 entity type determined in steps (c) in parallel by processing each element in container "ENTITY_T" Refer to the following screen.



The following screen displays the binding between workflow template "80000007" & "80000008".




Index [&WF_PARFOREACH_INDEX&] is used to access each element in container "ENTITY_T".

The main workflow 80000007 waits until all instance of sub-workflow is complete.

6. Activation of MOCR (Step 000338)

This step gets executed only when step (e) above is complete & “CR_WITHDRAWN” flag is not set in the workflow container. This step launch template 80000008 as sub-workflow to perform the final gatekeeper activation step. Once template “80000008” is complete the parent workflow “80000007” gets complete.

The following screen displays the binding between workflow template “80000007” & “80000008”. The BRF+ application ID is passed in the task container as a binding so the workflow template “80000008” knows which template to process when executed.



4.13.2. WS80000008 - Utopia Rule-Based Sub WF for MOCR


Use the following steps involved in this workflow template:

1. Start workflow.

The Utopia rule-based workflow is started as sub-workflow from template WS80000007 for each “Type 1” entity group in parallel.

2. Get Change Request Type.

This background tasks determines the change request type based on the change request number by executing the class method “GET_CR_TYPE” of class “CL_USMD_WF_SSW”. In the following screen, the binding between task and workflow container is displayed. Standard Task “TS60807944” is used at this workflow step “000004”.



Parameter	Type	Associated Type	Description
IV_CR_NUMBER	Importing	USMD_CREQUEST	Change Request
RV_CR_TYPE	Returning	USMD_CREQUEST_TYPE	Type of Change Request

3. Check assignment of processor to workflow.


The system checks whether a processor is assigned to the workflow (with or without a username).

If a processor is assigned, the system provides the values, users or methods that are needed for processing the task in the next workflow step.

If a processor is not assigned, the system launches BRFplus. When the workflow container "FUNC_ID" is not assigned then the workflow template executes the task "TS80000011".

TS80000011((000029- Path and Processor Finder)

This task calls the method "FIND_PATH_PROCESSOR" of class "/UGI7/USMD_WF_SSW". The following screen displays the binding between task and workflow container:



Parameter	Type	Associated Type	Description
IV_CR_NUMBER	Importing	USMD_CREQUEST	Change Request
IV_CR_TYPE	Importing	USMD_CREQUEST_TYPE	Type of Change Request
IV_STEP	Importing	USMD_CREQUEST_APPSTEP	Workflow Step Number
IV_ACTION	Importing	USMD_CREQUEST_ACTION	Action on User Interface of Change Request
IV_PARENT_STEP	Importing	USMD_CREQUEST_APPSTEP	Boolean Variable (X=true, =false, space=unknown)
IV_PAR_AGT_GRP_NUM	Importing	USMD_AGENT_GROUP	
IV_CR_PRIORITY	Importing	USMD_PRIORITY	Priority
IV_CR_REASON	Importing	USMD_REASON	Reason
IV_CR_REASON_REJ	Importing	USMD_REASON_REJ	Reason for Rejection
IV_CR_CREATOR	Importing	SWP_INITIA	Initiator of workflow instance
IV_ENTITY_TYPE	Importing	USMD_ENTITY	Entity Type
ET_USER_AGENT	Exporting	USMD_T_USER_AGENT_GROUP	

Parameter	Type	Associated Type	Description
ET_NON_USER_AGEN_T	Exporting	USMD_T_NON_USER_AGENT_GROUP	
ES_STEP_RSLT_MERGE_HANDLER	Exporting	USMD_S_STEP_RSLT_MERGE_HANDLER	
EV_CR_STATUS	Exporting	USMD_CREQUEST_STATUS	Status of Change Request
EV_NEXT_STEP	Exporting	USMD_CREQUEST_APPSTEP	Workflow Step Number
EV_EXP_COMP_HOURS	Exporting	INT2	2-byte integer (signed)
CT_MESSAGE	Changing	USMD_T_MESSAGE	Messages
CT_CONTEXT_TAB	Changing	USMD_T_GENERIC_CONTEXT	Generic Context Table

The system uses the values defined in the BRFplus decision tables to determine the next workflow step and to assign a processor, with or without a username. The value and the action of the next step depend on what is defined in the decision table for the previous step and what the previous action was. If the current workflow instance is the main workflow, the system also refreshes the status of the change request.

4. Determine whether single processing or parallel processing of change request is required.
The system determines the number of users or user groups to which the change request needs to be sent. For example, it might be necessary that the change request be sent for approval to users in the purchasing and accounting departments.

Single Processing


If single processing is necessary, the system, for example, sends the change request to a user and retrieves the relevant processing templates defined in the decision table for the next workflow step. For example, when the change request is created, the next step might determine that the change request be sent to the master data steward for approval.

The following task(s) exists within single processing:

TS80000006: (Step 0414-Notify by Email)

This task notifies the approver & other recipients based on the entries maintained in table view “/UGI7/V_EM_CONF” for the current workflow step type (determined from BRF+ application) by email. This is done by calling the method “NOTIFY_APPROVERS” of class “/UGI7/USMD_WF_SSW”.

The following screen displays the binding between workflow and task container.



Parallel Processing


Parallel processing of objects within a group of technical objects is not applicable for AIW MOCR workflow. Yet this section exists in workflow template since the template “80000008” is a copy of standard workflow “WS60800086”.

1. Activation of MOCR

Standard task “TS60808002” gets executed when the final gatekeeper opts “Activate CR” or “Activate & Launch New MOCR”. This task commits the MOCR data from staging area to active ECC database (hub/co-deploy model). At this point the MOCR data is ready for operational use.

2. Launch Sequence CR

This step executes the method “LAUNCH_SEQUENCE_CR” of class “/UGI7/USMD_WF_SSW” in the task “TS80000027(Step 405 Launch Sequence CR)”. This method copies all “Type 1” entities in the current MOCR to a new MOCR in draft mode. The following screen displays the binding between Workflow and task container



3. Check workflow completion

The system checks whether the indicator for completing a workflow has been set. If this is the case, the system completes the workflow. Otherwise, the system returns to step 3 and starts again.

Parameter	Type	Associated Type	Description
IV_CREQUEST	Importing	USMD_CREQUEST	Change Request
EV_SUCCESS	Exporting	BOOLE_D	Flag set when CR launched
EV_NEW_CR	Exporting	USMD_CREQUEST	Change Request
ET_MESSAGE	Exporting	USMD_T_MESSAGE	Messages

4.14. Email or Notifications Configuration

This section describes about Emails or Notifications sent out to actual recipients of the work item and additional recipient(s) in AIW.

The Email functionality is designed to support any Change Request Type and Workflow Step Types defined in MDGIMG configuration. The emails sent out are not actual workitem(s) but notifications for designated processor of the work item and any additional recipients to be notified at a BRF+ workflow step.

4.14.1. Disclaimer


The Email functionality is designed to work only for AIW BRF+ controlled workflow(s). This will not replace the Extended notifications defined in SAP.

4.14.2. Email Configuration

The following section describes the configuration that drives the email functionality.

4.14.2.1. Transparent Table

Table "/UGI7/EMAIL_CONF" stores the configuration detail of who should be notified, at what workflow step & the corresponding email template. The following screen displays the structure of table.



Field	Key	Ini...	Data element	Data Type	Length	Deci...	Short Description
MANDT	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	MANDT	CLNT	3	0	Client
USMD_CREQ_TYPE	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	USMD_CREQUEST_TYPE	CHAR	8	0	Type of Change Request
USMD_CR_STYPE	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	USMD_CREQUEST_AS_TYPE	CHAR	1	0	Change Request Step Type
USER_ROLE	<input type="checkbox"/>	<input type="checkbox"/>	/UGI7/RECEIVER_ROLE	INT1	3	0	Receiver Role
USER_TYPE	<input type="checkbox"/>	<input type="checkbox"/>	USMD_AGENT_TYPE	CHAR	2	0	Agent Type
USER_VALUE	<input type="checkbox"/>	<input type="checkbox"/>	USMD_AGENT_VALUE	CHAR	100	0	Agent Value
USMD_EMAIL_SUBJECT	<input type="checkbox"/>	<input type="checkbox"/>	/UGI7/EMAIL_SUB_OBJ	CHAR	60	0	Email Subject
USMD_EMAIL_BODY	<input type="checkbox"/>	<input type="checkbox"/>	/UGI7/EMAIL_BODY_OBJ	CHAR	60	0	Email Body

The fields are listed in detail in the following table:

Field	Description
USMD_CREQ_TYPE	MDG Change Request Type
USMD_CR_STYPE	Workflow step type (Approve / Revise / Process)
USMD_ROLE	Could be "Approver" or "Notify Only"
USMD_TYPE	Recipient type - could be "US" / "AG" / "S" / "C" / "O" / "SU"

Field	Description
USMD_VALUE	Recipient value for the type maintained in "USMD_TYPE"
USMD_EMAIL_SUBJECT	Email subject – name of the text object
USMD_EMAIL_BODY	Email body – name of the text object

4.14.2.2. Pre-delivered entries for Email Configuration

Type of Change Request	CR Step	Rec Role	Agent Type	Agent Value	Email Subject	Email Body
AIWEAM0P	20	1 Approver			/UGI7/EAM_SWN SUBJECT_REVISE	/UGI7/EAM_SWN_BODY_PROCE_REJ
AIWEAM0P	21	1 Approver			/UGI7/EAM_SWN SUBJECT_REVISE	/UGI7/EAM_SWN_BODY_PROCE_REJ
AIWEAM0P	22	1 Approver			/UGI7/EAM_SWN SUBJECT_REVISE	/UGI7/EAM_SWN_BODY_PROCE_REJ
AIWEAM0P	23	1 Approver			/UGI7/EAM_SWN SUBJECT_REVISE	/UGI7/EAM_SWN_BODY_PROCE_REJ
AIWEAM0P	24	1 Approver			/UGI7/EAM_SWN SUBJECT_REVISE	/UGI7/EAM_SWN_BODY_PROCE_REJ
AIWEAM0P	25	1 Approver			/UGI7/EAM_SWN SUBJECT_REVISE	/UGI7/EAM_SWN_BODY_PROCE_REJ
AIWEAM0P	26	1 Approver			/UGI7/EAM_SWN SUBJECT_REVISE	/UGI7/EAM_SWN_BODY_PROCE_REJ
AIWEAM0P	27	1 Approver			/UGI7/EAM_SWN SUBJECT_REVISE	/UGI7/EAM_SWN_BODY_PROCE_REJ
AIWEAM0P	28	1 Approver			/UGI7/EAM_SWN SUBJECT_REVISE	/UGI7/EAM_SWN_BODY_PROCE_REJ
AIWEAM0P	29	1 Approver			/UGI7/EAM_SWN SUBJECT_REVISE	/UGI7/EAM_SWN_BODY_PROCE_REJ
AIWEAM0P	30	1 Approver			/UGI7/EAM_SWN SUBJECT_REVISE	/UGI7/EAM_SWN_BODY_PROCE_REJ
AIWEAM0P	40	1 Approver			/UGI7/EAM_SWN SUBJECT_PROCES	/UGI7/EAM_SWN_BODY_PROCESS
AIWEAM0P	41	1 Approver			/UGI7/EAM_SWN SUBJECT_PROCES	/UGI7/EAM_SWN_BODY_PROCESS
AIWEAM0P	42	1 Approver			/UGI7/EAM_SWN SUBJECT_PROCES	/UGI7/EAM_SWN_BODY_PROCESS
AIWEAM0P	43	1 Approver			/UGI7/EAM_SWN SUBJECT_PROCES	/UGI7/EAM_SWN_BODY_PROCESS
AIWEAM0P	44	1 Approver			/UGI7/EAM_SWN SUBJECT_PROCES	/UGI7/EAM_SWN_BODY_PROCESS
AIWEAM0P	45	1 Approver			/UGI7/EAM_SWN SUBJECT_PROCES	/UGI7/EAM_SWN_BODY_PROCESS
AIWEAM0P	46	1 Approver			/UGI7/EAM_SWN SUBJECT_PROCES	/UGI7/EAM_SWN_BODY_PROCESS
AIWEAM0P	47	1 Approver			/UGI7/EAM_SWN SUBJECT_PROCES	/UGI7/EAM_SWN_BODY_PROCESS

Type of Change Request	CR Step	Rec Role	Agent Type	Agent Value	Email Subject	Email Body
AIWEAM0P	48	1 Approver			/UGI7/EAM_SWN SUBJECT PROCES	/UGI7/EAM_SWN BODY PROCESS
AIWEAM0P	49	1 Approver			/UGI7/EAM_SWN SUBJECT PROCES	/UGI7/EAM_SWN BODY PROCESS
AIWEAM0P	50	1 Approver			/UGI7/EAM_SWN SUBJECT PROCES	/UGI7/EAM_SWN BODY PROCESS
AIWEAM0P	80	1 Approver			/UGI7/EAM_SWN SUBJECT PROCES	/UGI7/EAM_SWN BODY PROCESS
AIWEAM0P	91	2 Notify Only	SU Special User (Initiator/Last-Step User)	INIT	/UGI7/EAM_SWN SUBJECT FINISH	/UGI7/EAM_SWN BODY FINISH
AIWEAM0S	20	1 Approver			/UGI7/EAM_SWN SUBJECT REVISE	/UGI7/EAM_SWN BODY PROCE REJ
AIWEAM0S	21	1 Approver			/UGI7/EAM_SWN SUBJECT REVISE	/UGI7/EAM_SWN BODY PROCE REJ
AIWEAM0S	22	1 Approver			/UGI7/EAM_SWN SUBJECT REVISE	/UGI7/EAM_SWN BODY PROCE REJ
AIWEAM0S	23	1 Approver			/UGI7/EAM_SWN SUBJECT REVISE	/UGI7/EAM_SWN BODY PROCE REJ
AIWEAM0S	24	1 Approver			/UGI7/EAM_SWN SUBJECT REVISE	/UGI7/EAM_SWN BODY PROCE REJ
AIWEAM0S	25	1 Approver			/UGI7/EAM_SWN SUBJECT REVISE	/UGI7/EAM_SWN BODY PROCE REJ
AIWEAM0S	26	1 Approver			/UGI7/EAM_SWN SUBJECT REVISE	/UGI7/EAM_SWN BODY PROCE REJ
AIWEAM0S	27	1 Approver			/UGI7/EAM_SWN SUBJECT REVISE	/UGI7/EAM_SWN BODY PROCE REJ
AIWEAM0S	28	1 Approver			/UGI7/EAM_SWN SUBJECT REVISE	/UGI7/EAM_SWN BODY PROCE REJ
AIWEAM0S	29	1 Approver			/UGI7/EAM_SWN SUBJECT REVISE	/UGI7/EAM_SWN BODY PROCE REJ
AIWEAM0S	30	1 Approver			/UGI7/EAM_SWN SUBJECT REVISE	/UGI7/EAM_SWN BODY PROCE REJ
AIWEAM0S	40	1 Approver			/UGI7/EAM_SWN SUBJECT PROCES	/UGI7/EAM_SWN BODY PROCESS
AIWEAM0S	41	1 Approver			/UGI7/EAM_SWN SUBJECT PROCES	/UGI7/EAM_SWN BODY PROCESS
AIWEAM0S	42	1 Approver			/UGI7/EAM_SWN SUBJECT PROCES	/UGI7/EAM_SWN BODY PROCESS
AIWEAM0S	43	1 Approver			/UGI7/EAM_SWN SUBJECT PROCES	/UGI7/EAM_SWN BODY PROCESS

Type of Change Request	CR Step	Rec Role	Agent Type	Agent Value	Email Subject	Email Body
AIWEAM0S	44	1 Approver			/UGI7/EAM_SWN SUBJECT PROCES	/UGI7/EAM_SWN BODY PROCESS
AIWEAM0S	45	1 Approver			/UGI7/EAM_SWN SUBJECT PROCES	/UGI7/EAM_SWN BODY PROCESS
AIWEAM0S	46	1 Approver			/UGI7/EAM_SWN SUBJECT PROCES	/UGI7/EAM_SWN BODY PROCESS
AIWEAM0S	47	1 Approver			/UGI7/EAM_SWN SUBJECT PROCES	/UGI7/EAM_SWN BODY PROCESS
AIWEAM0S	48	1 Approver			/UGI7/EAM_SWN SUBJECT PROCES	/UGI7/EAM_SWN BODY PROCESS
AIWEAM0S	49	1 Approver			/UGI7/EAM_SWN SUBJECT PROCES	/UGI7/EAM_SWN BODY PROCESS
AIWEAM0S	50	1 Approver			/UGI7/EAM_SWN SUBJECT PROCES	/UGI7/EAM_SWN BODY PROCESS
AIWEAM0S	80	1 Approver			/UGI7/EAM_SWN SUBJECT PROCES	/UGI7/EAM_SWN BODY PROCESS
AIWEAM0S	91	2 Notify Only	SU Special User (Initiator/Last-Step User)	INIT	/UGI7/EAM_SWN SUBJECT FINISH	/UGI7/EAM_SWN BODY FINISH
AIWEAMHY	20	1 Approver			/UGI7/EAM_SWN SUBJECT REVISE	/UGI7/EAM_SWN BODY PROCE REJ
AIWEAMHY	21	1 Approver			/UGI7/EAM_SWN SUBJECT REVISE	/UGI7/EAM_SWN BODY PROCE REJ
AIWEAMHY	22	1 Approver			/UGI7/EAM_SWN SUBJECT REVISE	/UGI7/EAM_SWN BODY PROCE REJ
AIWEAMHY	23	1 Approver			/UGI7/EAM_SWN SUBJECT REVISE	/UGI7/EAM_SWN BODY PROCE REJ
AIWEAMHY	24	1 Approver			/UGI7/EAM_SWN SUBJECT REVISE	/UGI7/EAM_SWN BODY PROCE REJ
AIWEAMHY	25	1 Approver			/UGI7/EAM_SWN SUBJECT REVISE	/UGI7/EAM_SWN BODY PROCE REJ
AIWEAMHY	26	1 Approver			/UGI7/EAM_SWN SUBJECT REVISE	/UGI7/EAM_SWN BODY PROCE REJ
AIWEAMHY	27	1 Approver			/UGI7/EAM_SWN SUBJECT REVISE	/UGI7/EAM_SWN BODY PROCE REJ
AIWEAMHY	28	1 Approver			/UGI7/EAM_SWN SUBJECT REVISE	/UGI7/EAM_SWN BODY PROCE REJ
AIWEAMHY	29	1 Approver			/UGI7/EAM_SWN SUBJECT REVISE	/UGI7/EAM_SWN BODY PROCE REJ
AIWEAMHY	30	1 Approver			/UGI7/EAM_SWN SUBJECT REVISE	/UGI7/EAM_SWN BODY PROCE REJ

Type of Change Request	CR Step	Rec Role	Agent Type	Agent Value	Email Subject	Email Body
AIWEAMHY	40	1 Approver			/UGI7/EAM_SWN SUBJECT PROCES	/UGI7/EAM_SWN BODY PROCESS
AIWEAMHY	41	1 Approver			/UGI7/EAM_SWN SUBJECT PROCES	/UGI7/EAM_SWN BODY PROCESS
AIWEAMHY	42	1 Approver			/UGI7/EAM_SWN SUBJECT PROCES	/UGI7/EAM_SWN BODY PROCESS
AIWEAMHY	43	1 Approver			/UGI7/EAM_SWN SUBJECT PROCES	/UGI7/EAM_SWN BODY PROCESS
AIWEAMHY	44	1 Approver			/UGI7/EAM_SWN SUBJECT PROCES	/UGI7/EAM_SWN BODY PROCESS
AIWEAMHY	45	1 Approver			/UGI7/EAM_SWN SUBJECT PROCES	/UGI7/EAM_SWN BODY PROCESS
AIWEAMHY	46	1 Approver			/UGI7/EAM_SWN SUBJECT PROCES	/UGI7/EAM_SWN BODY PROCESS
AIWEAMHY	47	1 Approver			/UGI7/EAM_SWN SUBJECT PROCES	/UGI7/EAM_SWN BODY PROCESS
AIWEAMHY	48	1 Approver			/UGI7/EAM_SWN SUBJECT PROCES	/UGI7/EAM_SWN BODY PROCESS
AIWEAMHY	49	1 Approver			/UGI7/EAM_SWN SUBJECT PROCES	/UGI7/EAM_SWN BODY PROCESS
AIWEAMHY	50	1 Approver			/UGI7/EAM_SWN SUBJECT PROCES	/UGI7/EAM_SWN BODY PROCESS
AIWEAMHY	80	1 Approver			/UGI7/EAM_SWN SUBJECT PROCES	/UGI7/EAM_SWN BODY PROCESS
AIWEAMHY	91	2 Notify Only	SU Special User (Initiator/Last-Step User)	INIT	/UGI7/EAM_SWN SUBJECT FINISH	/UGI7/EAM_SWN BODY FINISH


4.14.2.3. Maintenance View/IMG Node

Maintenance view “/UGI7/V_EM_CONF” is created to add new/change configuration of the emails in the table “/UGI7/EMAIL_CONF”.

This view can be accessed using the t-code SM30.

Alternatively, you can use the following IMG link.

1. Run t-code MDGIMG > Asset Information Workbench > Email Notification




4.14.3. Technical Details

This section of the document explains in detail about the technical developments made for the email functionality in AIW.

4.14.3.1. Standard Task - TS 80000006

The task “TS 80000006” executes the method “NOTIFY_APPROVERS” of the class “/UGI7/USMD_WF_SSW” to send email notification during change request workflow approval process. The task passes the following parameters from workflow container to class method.



4.14.3.2. Standard Text(s)

Standard text objects are created from t-code “SE61” in language “EN” for email subject and body for different workflow step types. The text objects were assigned in table “/UGI7/EMAIL_CONF” to be processed by the send email task of the workflow.

Use “Dialog Text” as the document class when using t-code SE61.

Text Object	Description
/UGI7/EAM_SWN SUBJECT PROCES	Subject of the email notification used in workflow step-type “Process / Approve”
/UGI7/EAM_SWN SUBJECT SEQCR	Subject of the email notification used in Sequence launch of CR.
/UGI7/EAM_SWN BODY PROCESS	Email content used in workflow step type “Process / Approve”
/UGI7/EAM_SWN BODY PROCE REJ	Email content used in workflow step-type “Revise”

Text Object	Description
/UGI7/EAM_SWN_BODY_SEQCR	Email content used in sequence launch of MOCR

4.14.3.3. Class Method to Send Email Notification

Class Method: /UGI7/USMD_WF_SSW->NOTIFY_APPROVERS

This method sends email notification to the recipients maintained in table “/UGI7/EMAIL_CONF” in “HTML” format.

The following describes the logic of the notification process:

- Determine the email configuration maintained for the change request type and workflow step type from table “/UGI7/EMAIL_CONF”.
- Determine the SAP user id, for each recipient maintained in table (apart from user type “US”)
- Call the method “SEND_MAIL” for the recipients determined in above step.

METHOD: SEND_MAIL

- Determine email ID of the SAP user by calling the method “GET_EMAIL_ID” (from user profile)
- Method “GET_VARIABLES_NOTIFICATIONS” return the contents related to Change Request & Workflow step to be embed in Email notification.
- Method “GET_TEXT_FROM_REPOSITORY” reads the text objects associated to the current workflow step type and replaces the text symbols (place holders) with the CR content determined in above step (b).
- Once the Email subject and body is built. the program sends the email by calling the method “SEND” of class “CL_BCS”.

4.14.4. Dependencies


The following list of objects that should exist for the email functionality to work without issues.

- The text objects maintained in table “/UGI7/EMAIL_CONF” should be valid (i.e. created).
- Email address should be maintained in user profile of the SAP user.
- SMTP nodes should be configured in t-code “SCOT”.


4.14.5. Sample Emails/Notifications

This section displays sample emails and notifications.

4.14.5.1. Approve or Process Change Request



4.14.5.2. Revise Change Request



4.15. SP01 Configuration


4.15.1. Pre-Requisite notes

Note	Description
2900157	Application logger base object produces incorrect messages

4.15.2. Common Configuration

- Execute transaction SM30.
- Enter Table name as /UGI7/AC_CUST.
- Click Maintain.
- Ensure MDG Pooling Active is set to 'X'.
- Ensure to put any UAIW process type of change request that you want to be the MOCR type.

Note: You can refer table USMD1601. Choose any change request type available here with usmd_process = UAIW.




Also schedule a job for report /UGI7/ACF_QUEUE_MOCR_CREATE at regular intervals in which you would like the MOCR creation to happen. You may want to consider using a Generic User as recommended by your BASIS team, which is used to execute this report. MOCR will appear to be created by this user.

4.15.3. Equipment Configuration


If multiple systems are connecting to Asset Central, you may want to consider keeping Equipment, Class and Characteristics Number Range Objects don't conflict each other across systems.

Make the following Changes mentioned below


1. Enter the tcode SE93 and enter the value(/SYCLO/CFG_MDO) and click on test button as shown below.



2. It will direct to Config panel: Mobile Data Object Settings webpage. Select “Asset Central Integration” from the dropdown Mobile Application Filter. As displayed below.



3. Note: Before proceeding to further steps kindly take backup manually as shown below.
 - a. Click on Data Filter tab, select Property Mapping and click on AC_PROPERTY_MAPPING*,
 - b. Copy all the Rule list records manually in word or notepad.
 - c. Click on Data Filter tab, select Property Mapping and click on AC_VALUE_MAPPING*, Copy all the Rule list records manually in word or notepad.
4. Select “SACI_EQUIPMENT_SYNC” from the drop down of SY-Synchronization MDO as shown below and replace the value of Data object Handler from “/ACI/CL_PM_EQUIPMENT_DO” to “/UGI7/CL_PM_EQUIPMENT_DO”. As displayed below.




The screenshot shows the SAP Asset Information Workbench interface. In the left sidebar, under 'Data Object Navigation Tree', the 'SY - Synchronization MDO' node is selected and highlighted with a red box. In the main content area, the 'Data Object Detail (Display Mode)' tab is active. The 'General Setting' tab is selected. Under 'Basic Data', the 'Mobile Data Object Id' is set to 'SACI_EQUIPMENT_SYNC'. The 'Description' field contains 'Asset Central Integration - Equipment Sync DO'. The 'Data Object Type' is 'Synchronization MDO'. The 'Mobile Application' is 'Asset Central Integration'. Under 'Cross System Synchronization Setting', the 'Target System Component' is 'SACI_AC_PUBLIC_CLOUD'. Under 'Data Object Handler Settings', the 'Data Object Handler' field is filled with '/UG17/CL_PM_EQUIPMENT_DO : DO class for EAM Utopia Equipment' and is also highlighted with a red box.


Once done, maintain the Values from the backup in AC_VALUE_MAPPING & AC_PROPERTY_MAPPING nodes in Data Filter tab.

Then follow the below steps for Document.

1. Enter the tcode SE93 and enter the value(/SYCLO/CFG_MDO) and click on test button as shown below.




2. It will direct to Config panel: Mobile Data Object Settings webpage. Select "Asset Central Integration" from the dropdown Mobile Application Filter. As displayed below.



The screenshot shows the 'ConfigPanel: Mobile Data Object Settings' webpage. The 'Mobile Application Filter' dropdown is set to 'Asset Central Integration'. The rest of the page includes a 'ConfigPanel Home' link and a 'Data Object Navigation Tree' sidebar.


3. Note: Before proceeding to further steps kindly take backup manually as shown below.
 - a. Click on Data Filter tab, select Property Mapping and click on AC_PROPERTY_MAPPING*. Copy all the Rule list records manually in word or notepad.
 - b. Click on Data Filter tab, select Property Mapping and click on AC_VALUE_MAPPING*. Copy all the Rule list records manually in word or notepad.

4. Select “SACI_DOCUMENT_SYNC” from the drop down of SY-Synchronization MDO as shown below and replace the value of Data object Handler from “/ACI/CL_PM_DOCUMENT_DO” to “/UGI7/CL_PM_DOCUMENT_DO”. As displayed below.





Follow below steps for making this change.

1. Click on Change button.




2. Select the Class ‘/UGI7/CL_PM_DOCUMENT_DO’ from the Drop-down list. Make sure that the ‘Push Enabled’ check box is checked and then Click ‘Save’.





The screenshot shows the SAP Asset Information Workbench interface. On the left, there is a navigation tree under 'Data Object Navigation Tree' with categories like Mobile Data Object, DT - Data Table, CT - Complex Table, DO - Standard Data Object, WF - Workflow Object, CM - Composite MDO, and SY - Synchronization MDO. Under SY, 'SACI_DOCUMENT_SYNC' is selected. The main panel is titled 'Data Object Detail (Display Mode)' and contains tabs for General Setting, ResultSet Field Selection, and Data Filter. Under General Setting, there are sections for Basic Data (Mobile Data Object Id: SACI_DOCUMENT_SYNC, Description: Asset Central Integration - Document Sync DO, Data Object Type: Synchronization MDO, Reference Business Object: Asset Central Integration), Cross System Synchronization Setting (Target System Component: SACI_AC_PUBLIC_CLOUD), Data Object Handler Settings (Data Object Handler: /UGI7/CL_PM_DOCUMENT_DO : UGI DO Handler - PM Document, Synchronize Method: EXEC_SYNCHRONI..., Push Enabled: checked), Exchange Object Settings (Exchange Object: SACI_DOCUMENT, Delta Calculation Time Offset (Seconds): 0), and Conversion Exit Setting.

3. The system will ask for a TR. Please give a TR and click 'Continue'.




Once done with above steps, maintain the Values from the backup in AC_VALUE_MAPPING & AC_PROPERTY_MAPPING nodes in Data Filter tab.

4.15.4. Functional Location Configuration


If multiple systems are connecting to Asset Central, you may want to consider keeping Functional Location Naming different across systems.

Make the following Changes mentioned below


1. Enter the tcode SE93 and enter the value(/SYCLO/CFG_MDO) and click on test button as shown below.



2. It will direct to Config panel: Mobile Data Object Settings webpage. Select “Asset Central Integration” from the dropdown Mobile Application Filter. As displayed below.




3. Note: Before proceeding to further steps kindly take backup manually as shown below.
- Click on Data Filter tab, select Property Mapping and click on AC_PROPERTY_MAPPING*,
 - Copy all the Rule list records manually in word or notepad.
 - Click on Data Filter tab, select Property Mapping and click on AC_VALUE_MAPPING*, Copy all the Rule list records manually in word or notepad.
4. Select “SACI_FUNCTIONAL_LOCATION_SYNC” from the drop down of SY-Synchronization MDO as shown below and replace the value of Data object Handler from “/ACI/CL_PM_FLOC_DO” to “/UGI7/CL_PM_FLOC_DO”. As displayed below.




Follow below steps for making this change.

1. Click on Change button.




The screenshot shows the SAP Asset Information Workbench interface. On the left, there is a navigation tree for 'Data Object Navigation Tree' under 'Mobile Data Object'. The selected node is 'SACI_FUNCTIONAL_LOCATION_SYNC'. The main panel is titled 'Data Object Detail (Display Mode)' with tabs for 'General Setting', 'ResultSet Field Selection', and 'Data Filter'. The 'General Setting' tab is active. It contains sections for 'Basic Data' (Mobile Data Object ID: SACI_FUNCTIONAL_LOCATION_SYNC, Description: Asset Central Integration - Functional Location Sync DO, Data Object Type: Synchronization MDO, Mobile Application: Asset Central Integration), 'Cross System Synchronization Setting' (Target System Component: SACI_AC_PUBLIC_CLOUD), 'Data Object Handler Settings' (Data Object Handler: /ACI/CL_PM_FLOC_DO : DO Handler - PM Function Location), 'Exchange Object Settings' (Exchange Object: SACI_FUNCTIONAL_LOCATI..., Delta Calculation Time Offset (Seconds): 0), and 'Conversion Exit Setting' (Enable Conv. Exit Overwrite:). The 'Change' button at the top right of the main panel is highlighted with a red box.

2. Select the Class '/UGI7/CL_PM_FLOC_DO' from the Drop-down list and Click 'Save'.




The screenshot shows the 'Data Object Detail (Change Mode)' screen. The 'Save' button at the top right is highlighted with a red box. A large black arrow points to the 'Data Object Handler' dropdown menu in the 'Data Object Handler Settings' section. The dropdown menu is open, showing several options, and the item '/UGI7/CL_PM_FLOC_DO : DO Handler - PM Function Location' is highlighted with a red box. Other visible options include '/ACI/CL_PM_FLOC_DO : DO Handler - PM Function Location', '/SYCLOCL_WM_STORAGETYPE_DO : DO Handler - WM Storage Type', '/SYCLOCL_WM_STORAGE_UNITS_DO : DO Handler - WM Level Stock Info', '/SYCLOCL_WM_ST_UNIT_TYPE_DO : DO Handler - WM Level Stock Info', '/SYCLOCL_WM_TRANSFERORDER_DO : DO Handler - WM Transfer Orders', '/SYCLOCL_WM_TRANSFERREQUEST_DO : DO Handler - WM Transfer Requirements', '/SYCLOCL_WM_WAREHOUSE_DO : DO Handler - WM Warehouse Info', '/UGI/CL_PM_DOCUMENT_DO : UGI DO Handler - PM Document', and '/UGI/CL_PM_EQUIPMENT_DO : DO class for EAM Utopia Equipment'.

3. Make sure that the 'Push Enabled' check box is checked as shown below.



The screenshot shows the 'Data Object Detail (Change Mode)' screen again. The 'Push Enabled' checkbox in the 'Data Object Handler Settings' section is highlighted with a green box. The 'Data Object Handler' dropdown is also highlighted with a red box. The rest of the screen is similar to the previous one, showing basic data, cross-system synchronization settings, and other handler configurations.

4. The system will ask for a TR. Please give a TR and click 'Continue'.



Once done with above steps, maintain the Values from the backup in AC_VALUE_MAPPING & AC_PROPERTY_MAPPING nodes in Data Filter tab.

4.15.5. Email Configurations

4.15.5.1. Standard Texts

This section of the document explains in detail about the technical developments made for the email functionality in AIW SP01.

Standard text objects are created from t-code “SE61” in language “EN” for email subject and body for IAM Integration.

Use “Dialog Text” as the document class when using t-code SE61.

Text Object	Description
/UGI7/ACF_AIW_CR_WIDRW_BODY	Body of the email notification to Asset Central User for Change Request Withdraw
/UGI7/ACF_AIW_CR_WIDRW_SUBJ	Subject of the email to Asset Central User for Change Request Withdraw
/UGI7/ACF_AIW_CR_OB_Rem_BODY	Body of the email notification to Asset Central User for Object Removal from Change Request
/UGI7/ACF_AIW_CR_OBJ_REMOVE	Subject of the email notification to Asset Central User for Object Removal from Change Request

4.16. System Compatibility

You can install AIW with the following configurations.

- S/4HANA 1809 FPS02 or 1909
- UGI EAM 1909

4.17. Final Steps

SAP and Utopia recommend regenerating the data model again at the end of these setup steps to ensure clear code generation.

i Note

Before you can run all Master Data Governance processes like Create Equipment, you need to assign the data model U1 to your user. Alternatively, the user administrator can maintain the following Personalization Parameter for your user profile: SAP Master Data Governance R_FMDM_MODEL.

If there are other data models active in your system, such as Financials (0G), Material Master (MM), or Business Partner/Customer/Supplier (BP) additional entries may appear in this list.